# **kayobe Documentation**

Release 17.3.1.dev5

**OpenStack Foundation** 

# **CONTENTS**

1	Over	Overview				
2	Kayo	ayobe				
	2.1	Features				
	2.2	Documentation				
	2.3	Release Notes				
	2.4	Bugs				
	2.5	Community				
	2.6	License				
3	Cont	ents				
	3.1	Getting Started				
	3.2	Architecture				
	3.3	Support Matrix				
	3.4	Installation				
	3.5	Usage				
	3.6	Configuration Guide				
	3.7	Deployment				
	3.8	Upgrading				
	3.9	Administration				
	3.10	Resources				
	3.11	Advanced Documentation				
	3.12	Contributor Guide				

## **CHAPTER**

# **ONE**

# **OVERVIEW**

Welcome to the Kayobe documentation, the official source of information for understanding and using Kayobe.

This documentation is maintained at opendev.org here. Feedback and contributions welcome, see *contributing* for information on how.

## **KAYOBE**

Kayobe enables deployment of containerised OpenStack to bare metal.

Containers offer a compelling solution for isolating OpenStack services, but running the control plane on an orchestrator such as Kubernetes or Docker Swarm adds significant complexity and operational overheads.

The hosts in an OpenStack control plane must somehow be provisioned, but deploying a secondary OpenStack cloud to do this seems like overkill.

Kayobe stands on the shoulders of giants:

- OpenStack bifrost discovers and provisions the cloud
- OpenStack kolla builds container images for OpenStack services
- OpenStack kolla-ansible delivers painless deployment and upgrade of containerised OpenStack services

To this solid base, kayobe adds:

- Configuration of cloud host OS & flexible networking
- · Management of physical network devices
- A friendly openstack-like CLI

All this and more, automated from top to bottom using Ansible.

## 2.1 Features

- Heavily automated using Ansible
- kayobe Command Line Interface (CLI) for cloud operators
- Deployment of a seed VM used to manage the OpenStack control plane
- Configuration of physical network infrastructure
- Discovery, introspection and provisioning of control plane hardware using OpenStack bifrost
- Deployment of an OpenStack control plane using OpenStack kolla-ansible
- Discovery, introspection and provisioning of bare metal compute hosts using OpenStack ironic and ironic inspector
- Virtualised compute using OpenStack nova

## kayobe Documentation, Release 17.3.1.dev5

- Containerised workloads on bare metal using OpenStack magnum
- Control plane monitoring using Prometheus and Grafana.
- Log aggregation using OpenSearch and OpenSearch Dashboards.

## 2.2 Documentation

https://docs.openstack.org/kayobe/latest/

## 2.3 Release Notes

https://docs.openstack.org/releasenotes/kayobe/

# **2.4 Bugs**

https://bugs.launchpad.net/kayobe

# 2.5 Community

OFTCs IRC channel: #openstack-kolla

## 2.6 License

Kayobe is distributed under the Apache 2.0 License.

#### CONTENTS

# 3.1 Getting Started

We advise new users start by reading the *Architecture* documentation first in order to understand Kayobes various components.

For users wishing to learn interactively we recommend starting at either the *all-in-one overcloud* deployment or the *A Universe From Nothing* deployment guide.

Once familiar with Kayobes constituent parts, move on to the *Installation* section to prepare a baremetal environment and then *Deployment* to deploy to it.

- Architecture The function of Kayobes host and networking components
- Installation The prerequisites and options for installing Kayobe
- Usage An introduction to the Kayobe CLI
- Configuration How to configure Kayobes various components
- Deployment- Using Kayobe to deploy OpenStack
- Upgrading Upgrading from one OpenStack release to another
- Administration Post-deploy administration tasks
- Resources External links to Kayobe resources
- Contributor Contributing to Kayobe and deploying Kayobe development environments

## 3.2 Architecture

## 3.2.1 Hosts in the System

In a system deployed by Kayobe we define a number of classes of hosts.

### **Ansible control host**

The Ansible control host is the host on which kayobe, kolla and kolla-ansible will be installed, and is typically where the cloud will be managed from.

#### Seed host

The seed host runs the bifrost deploy container and is used to provision the cloud hosts. By default, container images are built on the seed. Typically the seed host is deployed as a VM but this is not mandatory.

#### Infrastructure VM hosts

Infrastructure VMs (or Infra VMs) are virtual machines that may be deployed to provide supplementary infrastructure services. They may be for things like proxies or DNS servers that are dependencies of the Cloud hosts.

#### **Cloud hosts**

The cloud hosts run the OpenStack control plane, network, monitoring, storage, and virtualised compute services. Typically the cloud hosts run on bare metal but this is not mandatory.

#### Bare metal compute hosts

In a cloud providing bare metal compute services to tenants via ironic, these hosts will run the bare metal tenant workloads. In a cloud with only virtualised compute this category of hosts does not exist.

#### Note

In many cases the control and seed host will be the same, although this is not mandatory.

#### **Cloud Hosts**

Cloud hosts can further be divided into subclasses.

#### **Controllers**

Controller hosts run the OpenStack control plane services.

#### Network

Network hosts run the neutron networking services and load balancers for the OpenStack API services.

## Monitoring

Monitoring host run the control plane and workload monitoring services. Currently, kayobe does not deploy any services onto monitoring hosts.

#### Virtualised compute hypervisors

Virtualised compute hypervisors run the tenant Virtual Machines (VMs) and associated OpenStack services for compute, networking and storage.

## 3.2.2 Networks

Kayobes network configuration is very flexible but does define a few default classes of networks. These are logical networks and may map to one or more physical networks in the system.

#### Overcloud out-of-band network

Name of the network used by the seed to access the out-of-band management controllers of the bare metal overcloud hosts.

#### Overcloud provisioning network

The overcloud provisioning network is used by the seed host to provision the cloud hosts.

#### Workload out-of-band network

Name of the network used by the overcloud hosts to access the out-of-band management controllers of the bare metal workload hosts.

## Workload provisioning network

The workload provisioning network is used by the cloud hosts to provision the bare metal compute hosts.

#### Internal network

The internal network hosts the internal and admin OpenStack API endpoints.

#### Public network

The public network hosts the public OpenStack API endpoints.

#### **External network**

The external network provides external network access for the hosts in the system.

# 3.3 Support Matrix

## 3.3.1 Supported Operating Systems

Kayobe supports the following host Operating Systems (OS):

- Rocky Linux 9 (since Zed 13.0.0 release)
- Ubuntu Jammy 22.04 (since Zed 13.0.0 release)
- Ubuntu Noble 24.04 (since Dalmatian 17.0.0 release)

In addition to that CentOS Stream 9 host OS is functional, but not officially supported. Kolla does not publish CentOS Stream 9 images to Docker Hub/Quay.io, therefore users need to build them by themselves.

### Note

CentOS Stream 8 is no longer supported as a host OS. The Yoga release supports both CentOS Stream 8 and 9, and provides a route for migration.

#### Note

Rocky Linux 8 is no longer supported as a host OS. The Yoga release supports both Rocky Linux 8 and 9, and provides a route for migration.

## 3.3.2 Supported container images

For details of container image distributions supported by Kolla Ansible, see the support matrix.

For details of which images are supported on which distributions, see the Kolla support matrix.

## 3.4 Installation

Kayobe can be installed via the released Python packages on PyPI, or from source. Installing from PyPI ensures the use of well used and tested software, whereas installing from source allows for the use of unreleased or patched code. Installing from a Python package is supported from Kayobe 5.0.0 onwards.

## 3.4.1 Prerequisites

Currently Kayobe supports the following Operating Systems on the Ansible control host:

- CentOS Stream 9 (since Zed 13.0.0 release)
- Rocky Linux 9 (since Zed 13.0.0 release)
- Ubuntu Jammy 22.04 (since Zed 13.0.0 release)
- Ubuntu Noble 24.04 (since Dalmatian 17.0.0 release)

See the *support matrix* for details of supported Operating Systems for other hosts.

To avoid conflicts with python packages installed by the system package manager it is recommended to install Kayobe in a virtualenv. Ensure that the virtualenv python module is available on the Ansible control host. It is necessary to install the GCC compiler chain in order to build the extensions of some of kayobes python dependencies.

On CentOS/Rocky:

```
$ dnf install -y python3-devel gcc libffi-devel
```

On Ubuntu:

```
$ apt install -y python3-dev gcc libffi-dev python3-venv
```

If installing Kayobe from source, then Git is required for cloning and working with the source code repository.

On CentOS/Rocky:

```
$ dnf install -y git
```

On Ubuntu:

```
$ apt install -y git
```

On Ubuntu, ensure that /usr/bin/python points to a Python 3 interpreter:

```
$ apt install -y python-is-python3
```

## 3.4.2 Local directory structure

The directory structure for a Kayobe Ansible control host environment is configurable, but the following is recommended, where <br/>base\_path> is the path to a top level directory:

```
<base_path>/
    src/
    kayobe/
    kayobe-config/
    kolla-ansible/
    venvs/
    kayobe/
    kolla-ansible/
```

This pattern ensures that all dependencies for a particular environment are installed under a single top level path, and nothing is installed to a shared location. This allows for the option of using multiple Kayobe environments on the same control host.

Creation of a kayobe-config source code repository will be covered in the *configuration guide*. The Kolla Ansible source code checkout and Python virtual environment will be created automatically by kayobe.

Not all of these directories will be used in all scenarios - if Kayobe or Kolla Ansible are installed from a Python package then the source code repository is not required.

## 3.4.3 Installation from PyPI

This section describes how to install Kayobe from a Python package in a virtualenv. This is supported from Kayobe 5.0.0 onwards.

First, change to the top level directory, and make the directories for source code repositories and python virtual environments:

```
$ cd <base_path>
$ mkdir -p src venvs
```

Create a virtualenv for Kayobe:

```
$ python3 -m venv <base_path>/venvs/kayobe
```

Activate the virtualenv and update pip:

```
$ source <base_path>/venvs/kayobe/bin/activate
(kayobe) $ pip install -U pip
```

If using the latest version of Kayobe:

```
(kayobe) $ pip install kayobe
```

Alternatively, to install a specific release of Kayobe:

```
(kayobe) $ pip install kayobe==5.0.0
```

Finally, deactivate the virtualeny:

3.4. Installation 9

```
(kayobe) $ deactivate
```

#### 3.4.4 Installation from source

This section describes how to install Kayobe from source in a virtualenv.

First, change to the top level directory, and make the directories for source code repositories and python virtual environments:

```
$ cd <base_path>
$ mkdir -p src venvs
```

Next, obtain the Kayobe source code. For example:

```
$ cd <base_path>/src
$ git clone https://opendev.org/openstack/kayobe.git -b stable/2024.2
```

Create a virtualenv for Kayobe:

```
$ python3 -m venv <base_path>/venvs/kayobe
```

Activate the virtualenv and update pip:

```
$ source <base_path>/venvs/kayobe/bin/activate
(kayobe) $ pip install -U pip
```

Install Kayobe and its dependencies using the source code checkout:

```
(kayobe) $ cd <base_path>/src/kayobe
(kayobe) $ pip install .
```

Finally, deactivate the virtualenv:

```
(kayobe) $ deactivate
```

#### **Editable source installation**

From Kayobe 5.0.0 onwards it is possible to create an editable install of Kayobe. In an editable install, any changes to the Kayobe source tree will immediately be visible when running any Kayobe commands. To create an editable install, add the -e flag:

```
(kayobe) $ cd <base_path>/src/kayobe
(kayobe) $ pip install -e .
```

This is particularly useful when installing Kayobe for development.

# 3.5 Usage

### 3.5.1 Command Line Interface

#### Note

Where a prompt starts with (kayobe) it is implied that the user has activated the Kayobe virtualenv. This can be done as follows:

\$ source /path/to/venv/bin/activate

To deactivate the virtualenv:

(kayobe) \$ deactivate

To see information on how to use the kayobe CLI and the commands it provides:

```
(kayobe) $ kayobe help
```

As the kayobe CLI is based on the cliff package (as used by the openstack client), it supports tab autocompletion of subcommands. This can be activated by generating and then sourcing the bash completion script:

```
(kayobe) $ kayobe complete > kayobe-complete
(kayobe) $ source kayobe-complete
```

## **Working with Ansible Vault**

If Ansible Vault has been used to encrypt Kayobe configuration files, it will be necessary to provide the kayobe command with access to vault password. There are four options for doing this:

#### **Prompt**

Use kayobe --ask-vault-pass to prompt for the password.

#### File

Use kayobe --vault-password-file <file> to read the password from a (plain text) file.

## **Environment variable: KAYOBE\_VAULT\_PASSWORD**

Export the environment variable KAYOBE\_VAULT\_PASSWORD to read the password from the environment.

#### **Environment variable: ANSIBLE\_VAULT\_PASSWORD\_FILE**

Export the environment variable ANSIBLE\_VAULT\_PASSWORD\_FILE to read the password from a (plain text) file, with the path to that file being read from the environment.

3.5. Usage 11

## **Limiting Hosts**

Sometimes it may be necessary to limit execution of kayobe or kolla-ansible plays to a subset of the hosts. The --limit <SUBSET> argument allows the kayobe ansible hosts to be limited. The --kolla-limit <SUBSET> argument allows the kolla-ansible hosts to be limited. These two options may be combined in a single command. In both cases, the argument provided should be an Ansible host pattern, and will ultimately be passed to ansible-playbook as a --limit argument.

## **Tags**

Ansible tags provide a useful mechanism for executing a subset of the plays or tasks in a playbook. The --tags <TAGS> argument allows execution of kayobe ansible playbooks to be limited to matching plays and tasks. The --kolla-tags <TAGS> argument allows execution of kolla-ansible ansible playbooks to be limited to matching plays and tasks. The --skip-tags <TAGS> and --kolla-skip-tags <TAGS> arguments allow for avoiding execution of matching plays and tasks.

#### Check and diff mode

Ansible supports check and diff modes, which can be used to improve visibility into changes that would be made on target systems. The Kayobe CLI supports the --check argument, and since 11.0.0, the --diff argument. Note that these modes are not always guaranteed to work, when some tasks are dependent on earlier ones.

# 3.6 Configuration Guide

The configuration guide is split into two parts - scenarios and reference. The scenarios section provides information on configuring Kayobe for different scenarios. The reference section provides detailed information on many of Kayobes configuration options.

## 3.6.1 Configuration Scenarios

This section provides information on configuring Kayobe for different scenarios.

#### All in one scenario

## Note

This documentation is intended as a walk through of the configuration required for a minimal all-in-one overcloud host. If you are looking for an all-in-one environment for test or development, see *Automated Setup*.

This scenario describes how to configure an all-in-one controller and compute node using Kayobe. This is a very minimal setup, and not one that is recommended for a production environment, but is useful for learning about how to use and configure Kayobe.

## **Prerequisites**

This scenario requires a basic understanding of Linux, networking and OpenStack.


It also requires a single host running a *supported operating system* (VM or bare metal), with:

- 1 CPU
- 8GB RAM
- 40GB disk
- · at least one network interface that has Internet access

You will need access to a user account with passwordless sudo. The default user in a cloud image (e.g. centos or rocky or ubuntu) is typically sufficient. This user will be used to run Kayobe commands. It will also be used by Kayobe to bootstrap other user accounts.

#### Overview

An all in one environment consists of a single node that provides both control and compute services. There is no seed host, and no provisioning of the overcloud host. Customisation is minimal, in order to demonstrate the basic required configuration in Kayobe:



The networking in particular is relatively simple. The main interface of the overcloud host, labelled NIC 1 in the above diagram, will be used only for connectivity to the host and Internet access. A single Kayobe network called aio carries all control plane traffic, and is based on virtual networking that is local to the host

Later in this tutorial, we will create a dummy interface called dummy0, and plug it into a bridge called br0:

The use of a bridge here allows Kayobe to connect this network to the Open vSwitch network, while maintaining an IP address on the bridge. Ordinarily, dummy0 would be a NIC providing connectivity to a physical network. Were using a dummy interface here to keep things simple by using a fixed IP subnet, 192.168.33.0/24. The bridge will be assigned a static IP address of 192.168.33.3, and this address will by used for various things, including Ansible SSH access and OpenStack control plane traffic. Kolla Ansible will manage a Virtual IP (VIP) address of 192.168.33.2 on br0, which will be used for OpenStack API endpoints.

#### **Contents**

#### **Overcloud**

#### Note

This documentation is intended as a walk through of the configuration required for a minimal all-in-one overcloud host. If you are looking for an all-in-one environment for test or development, see *Automated Setup*.

## **Preparation**

Use the bootstrap user described in *prerequisites* to access the machine.

As described in the *overview*, we will use a bridge (br0) and a dummy interface (dummy0) for control plane networking. Use the following commands to create them and assign the bridge a static IP address of 192.168.33.3:

```
sudo ip 1 add br0 type bridge
sudo ip 1 set br0 up
sudo ip a add 192.168.33.3/24 dev br0
sudo ip 1 add dummy0 type dummy
sudo ip 1 set dummy0 up
sudo ip 1 set dummy0 master br0
```

This configuration is not persistent, and must be recreated if the VM is rebooted.

#### Installation

Follow the instructions in *Installation* to set up an Ansible control host environment. Typically this would be on a separate machine, but here we are keeping things as simple as possible.

## Configuration

Clone the kayobe-config git repository, using the correct branch for the release you are deploying. In this example we will use the stable/2024.2 branch.

```
cd <base path>/src
git clone https://opendev.org/openstack/kayobe-config.git -b stable/2024.2
cd kayobe-config
```

This repository is bare, and needs to be populated. The repository includes an example inventory, which should be removed:

```
git rm etc/kayobe/inventory/hosts.example
```

Create an Ansible inventory file and add the machine to it. In this example our machine is called controller0. Since this is an all-in-one environment, we add the controller to the compute group, however normally dedicated compute nodes would be used.

### Listing 1: etc/kayobe/inventory/hosts

The inventory directory also contains group variables for network interface configuration. In this example we will assume that the machine has a single network interface called dummy0. We will create a bridge called br0 and plug dummy0 into it. Replace the network interface configuration for the controllers group with the following:

# Listing 2: etc/kayobe/inventory/group\_vars/controllers/network-interfaces

```
# Controller interface on all-in-one network.
aio_interface: br0
# Interface dummy0 is plugged into the all-in-one network bridge.
(continues on next page)
```

In this scenario a single network called aio is used. We must therefore set the name of the default controller networks to aio:

Listing 3: etc/kayobe/networks.yml

```
# Kayobe network configuration.
→#
# Network role to network mappings.
# Map all networks to the all-in-one network.
# Name of the network used for admin access to the overcloud
#admin_oc_net_name:
admin_oc_net_name: aio
# Name of the network used by the seed to manage the bare metal overcloud
# hosts via their out-of-band management controllers.
#oob_oc_net_name:
# Name of the network used by the seed to provision the bare metal overcloud
#provision_oc_net_name:
# Name of the network used by the overcloud hosts to manage the bare metal
# compute hosts via their out-of-band management controllers.
#oob_wl_net_name:
# Name of the network used by the overcloud hosts to provision the bare metal
# workload hosts.
#provision_wl_net_name:
# Name of the network used to expose the internal OpenStack API endpoints.
#internal_net_name:
internal_net_name: aio
# List of names of networks used to provide external network access via
# Neutron.
# Deprecated name: external_net_name
# If external_net_name is defined, external_net_names will default to a list
# containing one item, external_net_name.
#external_net_names:
external_net_names:
```

(continues on next page)

```
# Name of the network used to expose the public OpenStack API endpoints.
#public_net_name:
public_net_name: aio
# Name of the network used by Neutron to carry tenant overlay network traffic.
#tunnel_net_name:
tunnel_net_name: aio
# Name of the network used to carry storage data traffic.
#storage_net_name:
storage_net_name: aio
# Name of the network used to carry storage management traffic.
#storage_mgmt_net_name:
storage_mgmt_net_name: aio
# Name of the network used to carry swift storage data traffic.
#swift storage net name:
# Name of the network used to carry swift storage replication traffic.
#swift_storage_replication_net_name:
# Name of the network used to perform hardware introspection on the bare metal
# workload hosts.
#inspection_net_name:
# Name of the network used to perform cleaning on the bare metal workload
# hosts
#cleaning_net_name:
. #
# Network definitions.
```

Next the aio network must be defined. This is done using the various attributes described in *Network Configuration*. These values should be adjusted to match the environment. The aio\_vip\_address variable should be a free IP address in the same subnet for the virtual IP address of the OpenStack API.

Listing 4: etc/kayobe/networks.yml

(continues on next page)

Kayobe will automatically allocate IP addresses. In this case however, we want to ensure that the host uses the same IP address it has currently, to avoid loss of connectivity. We can do this by populating the network allocation file. Use the correct hostname and IP address for your environment.

Listing 5: etc/kayobe/network-allocation.yml

```
---
aio_ips:
controller0: 192.168.33.3
```

The default OS distribution in Kayobe is CentOS. If using an Ubuntu host, set the os\_distribution variable in etc/kayobe/globals.yml to ubuntu or rocky if using Rocky Linux..

Listing 6: etc/kayobe/globals.yml

```
os_distribution: "ubuntu"
```

Kayobe uses a bootstrap user to create a stack user account. By default, this user is centos on CentOS, rocky on Rocky and ubuntu on Ubuntu, in line with the default user in the official cloud images. If you are using a different bootstrap user, set the controller\_bootstrap\_user variable in etc/kayobe/controllers.yml. For example, to set it to cloud-user (as seen in MAAS):

Listing 7: etc/kayobe/controllers.yml

```
controller_bootstrap_user: "cloud-user"
```

By default, on systems with SELinux disabled, Kayobe will put SELinux in permissive mode and reboot the system to apply the change. In a test or development environment this can be a bit disruptive, particularly when using ephemeral network configuration. To avoid rebooting the system after enabling SELinux, set selinux\_do\_reboot to false in etc/kayobe/globals.yml.

Listing 8: etc/kayobe/globals.yml

```
selinux_do_reboot: false
```

In a development environment, we may wish to tune some Kolla Ansible variables. Using QEMU as the virtualisation type will be necessary if KVM is not available. Reducing the number of OpenStack service workers helps to avoid using too much memory.

Listing 9: etc/kayobe/kolla/globals.yml

```
# Most development environments will use nested virtualisation, and we can't
# guarantee that nested KVM support is available. Use QEMU as a lowest common
# denominator.
```

(continues on next page)

```
nova_compute_virt_type: qemu

# Reduce the control plane's memory footprint by limiting the number of worker
# processes to one per-service.
openstack_service_workers: "1"
```

We can see the changes that have been made to the configuration.

```
cd <base path>/src/kayobe-config
git status

On branch master
Your branch is up to date with 'origin/master'.

Changes to be committed:
   (use "git restore --staged <file>..." to unstage)
        deleted: etc/kayobe/inventory/hosts.example

Changes not staged for commit:
   (use "git add <file>..." to update what will be committed)
   (use "git restore <file>..." to discard changes in working directory)
        modified: etc/kayobe/globals.yml
        modified: etc/kayobe/inventory/group_vars/controllers/network-interfaces
        modified: etc/kayobe/hosts/yml

Untracked files:
   (use "git add <file>..." to include in what will be committed)
        etc/kayobe/inventory/hosts
        etc/kayobe/network-allocation.yml
```

The git diff command is also helpful. Once all configuration changes have been made, they should be committed to the kayobe-config git repository.

```
cd <base path>/src/kayobe-config
git add etc/kayobe/inventory/hosts etc/kayobe/network-allocation.yml
git add --update
git commit -m "All in one scenario config"
```

In a real environment these changes would be pushed to a central repository.

## **Deployment**

We are now ready to perform a deployment.

Activate the Kayobe virtual environment:

```
cd <base path>/venvs/kayobe source bin/activate
```

#### Activate the Kayobe configuration environment:

```
cd <base path>/src/kayobe-config source kayobe-env
```

#### Bootstrap the control host:

```
kayobe control host bootstrap
```

## Configure the overcloud host:

```
kayobe overcloud host configure
```

After this command has run, some files in the kayobe-config repository will have changed. Kayobe performs static allocation of IP addresses, and tracks them in etc/kayobe/network-allocation. yml. Normally there may be changes to this file, but in this case we manually added the IP address of controller0 earlier. Kayobe uses tools provided by Kolla Ansible to generate passwords, and stores them in etc/kayobe/kolla/passwords.yml. It is important to track changes to this file.

```
cd <base path>/src/kayobe-config
git add etc/kayobe/kolla/passwords.yml
git commit -m "Add autogenerated passwords for Kolla Ansible"
```

## Pull overcloud container images:

```
kayobe overcloud container image pull
```

#### Deploy overcloud services:

```
kavobe overcloud service deploy
```

#### **Testing**

The init-runonce script provided by Kolla Ansible (not for production) can be used to setup some resources for testing. This includes:

- · some flavors
- · a cirros image
- · an external network
- a tenant network and router
- security group rules for ICMP, SSH, and TCP ports 8000 and 8080

- · an SSH key
- increased quotas

For the external network, use the same subnet as before, with an allocation pool range containing free IP addresses:

```
pip install python-openstackclient
export EXT_NET_CIDR=192.168.33.0/24
export EXT_NET_GATEWAY=192.168.33.3
export EXT_NET_RANGE="start=192.168.33.4,end=192.168.33.254"
source "${KOLLA_CONFIG_PATH:-/etc/kolla}/admin-openrc.sh"
${KOLLA_SOURCE_PATH}/tools/init-runonce
```

Create a server instance, assign a floating IP address, and check that it is accessible.

```
openstack server create --image cirros --flavor m1.tiny --key-name mykey --

→network demo-net demo1

openstack floating ip create public1
```

The floating IP address is displayed after it is created, in this example it is 192.168.33.4:

```
openstack server add floating ip demo1 192.168.33.4 ssh cirros@192.168.33.4
```

## 3.6.2 Configuration Reference

This section provides detailed information on many of Kayobes configuration options.

#### **Kayobe Configuration**

This section covers configuration of Kayobe. As an Ansible-based project, Kayobe is for the most part configured using YAML files.

## **Configuration Location**

Kayobe configuration is by default located in /etc/kayobe on the Ansible control host. This location can be overridden to a different location to avoid touching the system configuration directory by setting the environment variable KAYOBE\_CONFIG\_PATH. Similarly, kolla configuration on the Ansible control host will by default be located in /etc/kolla and can be overridden via KOLLA\_CONFIG\_PATH.

### **Configuration Directory Layout**

The Kayobe configuration directory contains Ansible extra-vars files and the Ansible inventory. An example of the directory structure is as follows:

```
extra-vars1.yml
extra-vars2.yml
inventory/
group_vars/
group1-vars
group2-vars
groups
host_vars/
host1-vars
host2-vars
```

### **Configuration Patterns**

Ansibles variable precedence rules are fairly well documented and provide a mechanism we can use for providing site localisation and customisation of OpenStack in combination with some reasonable default values. For global configuration options, Kayobe typically uses the following patterns:

- Inventory group variables for the *all* group in <kayobe repo>/ansible/inventory/group\_vars/all/\* set **global defaults**. These files should not be modified.
- Inventory group variables for other groups in <kayobe repo>/ansible/inventory/ group\_vars/<group>/\* set defaults for some subsets of hosts. These files should not be modified.
- Extra-vars files in \${KAYOBE\_CONFIG\_PATH}/\*.yml set custom values for global variables and should be used to apply global site localisation and customisation. By default these variables are commented out.

Additionally, variables can be set on a per-group or per-host basis using inventory group or host variables files in \${KAYOBE\_CONFIG\_PATH}/inventory/group\_vars/\* or \${KAYOBE\_CONFIG\_PATH}/inventory/host\_vars/\* respectively. It should be noted that variables set in extra-vars files take precedence over per-host variables.

#### **Configuring Kayobe**

The kayobe-config git repository contains a Kayobe configuration directory structure and unmodified configuration files. This repository can be used as a mechanism for version controlling Kayobe configuration. As Kayobe is updated, the configuration should be merged to incorporate any upstream changes with local modifications.

Alternatively, the baseline Kayobe configuration may be copied from a checkout of the Kayobe repository to the Kayobe configuration path:

```
$ mkdir -p ${KAYOBE_CONFIG_PATH:-/etc/kayobe/}
$ cp -r etc/kayobe/* ${KAYOBE_CONFIG_PATH:-/etc/kayobe/}
```

Once in place, each of the YAML and inventory files should be manually inspected and configured as required.

## **Inventory**

The inventory should contain the following hosts:

#### **Ansible Control host**

This should be localhost.

## **Seed hypervisor**

If provisioning a seed VM, a host should exist for the hypervisor that will run the VM, and should be a member of the seed-hypervisor group.

#### Seed

The seed host, whether provisioned as a VM by Kayobe or externally managed, should exist in the seed group.

Cloud hosts and bare metal compute hosts are not required to exist in the inventory if discovery of the control plane hardware is planned, although entries for groups may still be required.

Use of advanced control planes with multiple server roles and customised service placement across those servers is covered in *Control Plane Service Placement*.

#### Site Localisation and Customisation

Site localisation and customisation is applied using Ansible extra-vars files in \${KAYOBE\_CONFIG\_PATH}/\*.yml.

## **Configuration of Ansible**

Ansible configuration is described in detail in the Ansible documentation. In addition to the standard locations, Kayobe supports using an Ansible configuration file located in the Kayobe configuration at \${KAYOBE\_CONFIG\_PATH}/ansible.cfg. Note that if the ANSIBLE\_CONFIG environment variable is specified it takes precedence over this file.

#### **Encryption of Secrets**

Kayobe supports the use of Ansible vault to encrypt sensitive information in its configuration. The ansible-vault tool should be used to manage individual files for which encryption is required. Any of the configuration files may be encrypted. Since encryption can make working with Kayobe difficult, it is recommended to follow best practice, adding a layer of indirection and using encryption only where necessary.

#### Location of data files

Kayobe needs to know where to find any files not contained within its python package; this includes its Ansible playbooks and any other files it needs for runtime operation. These files are known collectively as data files.

Kayobe will attempt to detect the location of its data files automatically. However, if you have installed kayobe to a non-standard location this auto-detection may fail. It is possible to manually override the path using the environment variable: KAYOBE\_DATA\_FILES\_PATH. This should be set to a path with the following structure:

```
requirements.yml
ansible/
roles/
...
```

Where ansible is the ansible directory from the source checkout and ... is an elided representation of any files and subdirectories contained within that directory.

#### **Ansible**

Ansible configuration is described in detail in the Ansible documentation. It is explained elsewhere in this guide how to configure Ansible for *Kayobe* and *Kolla Ansible*.

In this section we cover some options for tuning Ansible for performance and scale.

## SSH pipelining

SSH pipelining is disabled in Ansible by default, but is generally safe to enable, and provides a reasonable performance improvement.

Listing 10: \$KAYOBE\_CONFIG\_PATH/ansible.cfg

```
[ssh_connection]
pipelining = True
```

### **Forks**

24

By default Ansible executes tasks using a fairly conservative 5 process forks. This limits the parallelism that allows Ansible to scale. Most Ansible control hosts will be able to handle far more forks than this. You will need to experiment to find out the CPU, memory and IO limits of your machine.

For example, to increase the number of forks to 20:

Listing 11: \$KAYOBE\_CONFIG\_PATH/ansible.cfg

```
[defaults]
forks = 20
```

## **Fact caching**

#### Note

Fact caching will not work correctly in Kayobe prior to the Ussuri release.

By default, Ansible gathers facts for each host at the beginning of every play, unless gather\_facts is set to false. With a large number of hosts this can result in a significant amount of time spent gathering facts.

One way to improve this is through Ansibles support for fact caching. In order to make this work with Kayobe, it is necessary to change Ansibles gathering configuration option to smart. Additionally, it is necessary to use separate fact caches for Kayobe and Kolla Ansible due to some of the facts (e.g. ansible\_facts.user\_uid and ansible\_facts.python) differing.

## **Example**

In the following example we configure Kayobe and Kolla Ansible to use fact caching using the jsonfile cache plugin.

Listing 12: \$KAYOBE\_CONFIG\_PATH/ansible.cfg

```
[defaults]
gathering = smart
fact_caching = jsonfile
fact_caching_connection = /tmp/kayobe-facts
```

Listing 13: \$KAYOBE\_CONFIG\_PATH/kolla/ansible.cfg

```
[defaults]
gathering = smart
fact_caching = jsonfile
fact_caching_connection = /tmp/kolla-ansible-facts
```

You may also wish to set the expiration timeout for the cache via [defaults] fact\_caching\_timeout.

#### Fact gathering

## **Fact filtering**

Filtering of facts can be used to speed up Ansible. Environments with many network interfaces on the network and compute nodes can experience very slow processing with Kayobe and Kolla Ansible. This happens due to the processing of the large per-interface facts with each task. To avoid storing certain facts, we can use the kayobe\_ansible\_setup\_filter variable, which is used as the filter argument to the setup module.

One case where this is particularly useful is to avoid collecting facts for virtual tap (beginning with t) and bridge (beginning with q) interfaces created by Neutron. These facts are large map values which can

consume a lot of resources on the Ansible control host. Kayobe and Kolla Ansible typically do not need to reference them, so they may be filtered. For example, to avoid collecting facts beginning with q or t:

Listing 14: \$KAYOBE\_CONFIG\_PATH/globals.yml

```
kayobe_ansible_setup_filter: "ansible_[!qt]*"
```

Similarly, for Kolla Ansible (notice the similar but different file names):

Listing 15: \$KAYOBE\_CONFIG\_PATH/kolla/globals.yml

```
kolla_ansible_setup_filter: "ansible_[!qt]*"
```

This causes Ansible to collect but not store facts matching that pattern, which includes the virtual interface facts. Currently we are not referencing other facts matching the pattern within Kolla Ansible. Note that including the *ansible* prefix causes meta facts module\_setup and gather\_subset to be filtered, but this seems to be the only way to get a good match on the interface facts.

The exact improvement will vary, but has been reported to be as large as 18x on systems with many virtual interfaces.

## **Fact gathering subsets**

It is also possible to configure which subsets of facts are gathered, via kayobe\_ansible\_setup\_gather\_subset, which is used as the gather\_subset argument to the setup module. For example, if one wants to avoid collecting facts via facter:

Listing 16: \$KAYOBE\_CONFIG\_PATH/globals.yml

```
kayobe_ansible_setup_gather_subset: "all,!facter"
```

Similarly, for Kolla Ansible (notice the similar but different file names):

Listing 17: \$KAYOBE\_CONFIG\_PATH/kolla/globals.yml

```
kolla_ansible_setup_gather_subset: "all,!facter"
```

## Max failure percentage

It is possible to specify a maximum failure percentage using kayobe\_max\_fail\_percentage. By default this is undefined, which is equivalent to a value of 100, meaning that Ansible will continue execution until all hosts have failed or completed. For example:

Listing 18: \$KAYOBE\_CONFIG\_PATH/globals.yml

```
kayobe_max_fail_percentage: 50
```

A max fail percentage may be set for the kayobe \* host configure commands using host\_configure\_max\_fail\_percentage, or for a specific playbook using <playbook>\_max\_fail\_percentage where <playbook> is the playbook name with dashes replaced with underscores and without the .yml extension. For example:

## Listing 19: \$KAYOBE\_CONFIG\_PATH/globals.yml

```
kayobe_max_fail_percentage: 50
host_configure_max_fail_percentage: 25
time_max_fail_percentage: 100
```

#### **OS Distribution**

As of the Wallaby 10.0.0 release, Kayobe supports multiple Operating System (OS) distributions. See the *support matrix* for a list of supported OS distributions. The same OS distribution should be used throughout the system.

The os\_distribution variable in etc/kayobe/globals.yml can be used to set the OS distribution to use. It may be set to either centos or or rocky or ubuntu, and defaults to rocky.

The os\_release variable in etc/kayobe/globals.yml can be used to set the release of the OS. When os\_distribution is set to centos it may be set to 9-stream, and this is its default value. When os\_distribution is set to ubuntu it may be set to noble, and this is its default value. When os\_distribution is set to rocky it may be set to 9, and this is its default value.

These variables are used to set various defaults, including:

- · Bootstrap users
- Overcloud host root disk image build configuration
- Seed VM root disk image
- Kolla base container image

## **Example: using Ubuntu**

In the following example, we set the OS distribution to ubuntu:

Listing 20: globals.yml

```
os_distribution: "ubuntu"
```

## **Example: using Rocky**

In the following example, we set the OS distribution to rocky:

## Listing 21: globals.yml

os\_distribution: "rocky"

## **Physical Network Configuration**

Kayobe supports configuration of physical network devices. This feature is optional, and this section may be skipped if network device configuration will be managed via other means.

Devices are added to the Ansible inventory, and configured using Ansibles networking modules. Configuration is applied via the kayobe physical network configure command. See *Physical Network* for details.

The following switch operating systems are currently supported:

- Arista EOS
- Cumulus Linux (via Network Command Line Utility (NCLU))
- Cumulus Linux (via NVIDIA User Experience command line utility (NVUE))
- Dell OS 6
- Dell OS 9
- Dell OS 10
- Dell PowerConnect
- Juniper Junos OS
- · Mellanox MLNX OS

## Note

When developing switch configuration, it can be helpful to see what commands will be generated. This can be done using the --display parameter for kayobe physical network configure, which will output switch global and port configuration as terminal output without applying it.

## **Adding Devices to the Inventory**

Network devices should be added to the Kayobe Ansible inventory, and should be members of the switches group.

Listing 22: inventory/hosts

## [switches]

switch0

switch1

In some cases it may be useful to differentiate different types of switches, For example, a mgmt network might carry out-of-band management traffic, and a ctl network might carry control plane traffic. A group could be created for each of these networks, with each group being a child of the switches group.

## Listing 23: inventory/hosts

```
[switches:children]
mgmt-switches
ctl-switches

[mgmt-switches]
switch0

[ctl-switches]
switch1
```

## **Network Device Configuration**

Configuration is typically specific to each network device. It is therefore usually best to add a host\_vars file to the inventory for each device. Common configuration for network devices can be added in a group\_vars file for the switches group or one of its child groups.

Listing 24: inventory/host\_vars/switch0

```
# Host configuration for switch0
ansible_host: 1.2.3.4
```

Listing 25: inventory/host\_vars/switch1

```
# Host configuration for switch1
ansible_host: 1.2.3.5
```

Listing 26: inventory/group\_vars/switches

```
# Group configuration for 'switches' group.
ansible_user: alice
```

#### **Common Configuration Variables**

The type of switch should be configured via the switch\_type variable. See *Device-specific Configuration Variables* for details of the value to set for each device type.

ansible\_host should be set to the management IP address used to access the device. ansible\_user should be set to the user used to access the device.

Global switch configuration is specified via the switch\_config variable. It should be a list of configuration lines to apply.

Per-interface configuration is specified via the switch\_interface\_config variable. It should be an object mapping switch interface names to configuration objects. Each configuration object contains a

description item and a config item. The config item should contain a list of per-interface configuration lines.

The switch\_interface\_config\_enable\_discovery and switch\_interface\_config\_disable\_discovery variables take the same format as the switch\_interface\_config variable. They define interface configuration to apply to enable or disable hardware discovery of bare metal compute nodes.

Listing 27: inventory/host\_vars/switch0

Network device configuration can become quite repetitive, so it can be helpful to define group variables that can be referenced by multiple devices. For example:

Listing 28: inventory/group\_vars/switches

```
# Group configuration for the 'switches' group.

switch_config_default:
        - default global config line 1
        - default global config line 2

switch_interface_config_controller:
        - controller interface config line 1
        - controller interface config line 2

switch_interface_config_compute:
        - compute interface config line 1
        - compute interface config line 2
```

## Listing 29: inventory/host\_vars/switch0

```
ansible_host: 1.2.3.4

ansible_user: alice

switch_config: "{{ switch_config_default }}"

switch_interface_config:
  interface=0:
    description: controller0
    config: "{{ switch_interface_config_controller }}"
  interface=1:
    description: compute0
    config: "{{ switch_interface_config_compute }}"
```

## **Support for Older Devices**

Some network devices may use SSH key exchange algorithms that are no longer supported by the Ansible control host. This will cause ssh-keyscan to fail, preventing Kayobe from configuring the devices. To work around this, set switch\_skip\_keyscan to true for the affected devices. The SSH known hosts file on the Ansible control host will need to be populated manually.

## **Device-specific Configuration Variables**

#### **Arista EOS**

Configuration for these devices is applied using the arista-switch Ansible role in Kayobe. The role configures Arista switches using the eos Ansible modules.

switch\_type should be set to arista.

- ansible\_host is the hostname or IP address. Optional.
- ansible\_user is the SSH username.
- ansible\_ssh\_pass is the SSH password.
- ansible\_connection should be ansible.netcommon.network\_cli.
- ansible\_network\_os should be arista.eos.eos.
- ansible\_become should be true.
- ansible\_become\_method should be enable.

## **Cumulus Linux (with NCLU)**

Configuration for these devices is applied using the nclu Ansible module.

switch\_type should be set to nclu.

## **Cumulus Linux (with NVUE)**

Configuration for these devices is applied using the nvidia.nvue.command Ansible module. switch\_type should be set to nvue.

## **SSH** configuration

As with any non-switch host in the inventory, the nclu and nvidia.nvue.command modules rely on the default connection parameters used by Ansible:

- ansible\_host is the hostname or IP address. Optional.
- ansible\_user is the SSH username.

## Dell OS6, OS9, and OS10

Configuration for these devices is applied using the dellos6\_config, dellos9\_config, and dellos10\_config Ansible modules.

switch\_type should be set to dellos6, dellos9, or dellos10.

switch\_config\_save may be set to true to enable saving configuration after it has been applied.

#### **Provider**

- ansible\_host is the hostname or IP address. Optional.
- ansible\_user is the SSH username.
- ansible\_ssh\_pass is the SSH password.
- switch\_auth\_pass is the enable password.

Alternatively, set switch\_dellos\_provider to the value to be passed as the provider argument to the dellos\*\_config module.

#### **Dell PowerConnect**

Configuration for these devices is applied using the stackhpc.network. dell\_powerconnect\_switch Ansible role. The role uses the expect Ansible module to automate interaction with the switch CLI via SSH.

switch\_type should be set to dell-powerconnect.

# **Provider**

- ansible\_host is the hostname or IP address. Optional.
- ansible\_user is the SSH username.
- switch\_auth\_pass is the SSH password.

# **Juniper Junos OS**

Configuration for these devices is applied using the junos\_config Ansible module.

switch\_type should be set to junos.

switch\_junos\_config\_format may be used to set the format of the configuration. The variable is passed as the src\_format argument to the junos\_config module. The default value is text.

#### **Provider**

- ansible\_host is the hostname or IP address. Optional.
- ansible\_user is the SSH username.
- ansible\_ssh\_pass is the SSH password. Mutually exclusive with ansible\_ssh\_private\_key\_file.
- ansible\_ssh\_private\_key\_file is the SSH private key file. Mutually exclusive with ansible\_ssh\_pass.
- switch\_junos\_timeout may be set to a timeout in seconds for communicating with the device.

Alternatively, set switch\_junos\_provider to the value to be passed as the provider argument to the junos\_config module.

### **Mellanox MLNX OS**

Configuration for these devices is applied using the stackhpc.network.mellanox\_switch Ansible role. The role uses the expect Ansible module to automate interaction with the switch CLI via SSH.

switch\_type should be set to mellanox.

#### **Provider**

- ansible\_host is the hostname or IP address. Optional.
- ansible\_user is the SSH username.
- switch\_auth\_pass is the SSH password.

# **Network Configuration**

Kayobe provides a flexible mechanism for configuring the networks in a system. Kayobe networks are assigned a name which is used as a prefix for variables that define the networks attributes. For example, to configure the cidr attribute of a network named arpanet, we would use a variable named arpanet\_cidr.

### **Global Network Configuration**

Global network configuration is stored in \${KAYOBE\_CONFIG\_PATH}/networks.yml. The following attributes are supported:

#### cidr

CIDR representation (<IP>//sprefix length>) of the networks IP subnet.

### allocation\_pool\_start

IP address of the start of Kayobes allocation pool range.

# allocation\_pool\_end

IP address of the end of Kayobes allocation pool range.

### inspection\_allocation\_pool\_start

IP address of the start of ironic inspectors allocation pool range.

### inspection\_allocation\_pool\_end

IP address of the end of ironic inspectors allocation pool range.

# neutron\_allocation\_pool\_start

IP address of the start of neutrons allocation pool range.

### neutron\_allocation\_pool\_end

IP address of the end of neutrons allocation pool range.

#### gateway

IP address of the networks default gateway.

# inspection\_gateway

IP address of the gateway for the hardware introspection network.

### neutron\_gateway

IP address of the gateway for a neutron subnet based on this network.

#### vlan

VLAN ID.

#### mtu

Maximum Transmission Unit (MTU).

# vip\_address

### Note

Use of the vip\_address attribute is deprecated. Instead use kolla\_internal\_vip\_address and kolla\_external\_vip\_address.

Virtual IP address (VIP) used by API services on this network.

# fqdn

#### Note

Use of the fqdn attribute is deprecated. Instead use kolla\_internal\_fqdn and kolla\_external\_fqdn.

Fully Qualified Domain Name (FQDN) used by API services on this network.

#### routes

#### Note

options is not currently supported on Ubuntu.

List of static IP routes. Each item should be a dict containing the item cidr, and optionally gateway, table and options. cidr is the CIDR representation of the routes destination. gateway is the IP address of the next hop. table is the name or ID of a routing table to which the route will be added. options is a list of option strings to add to the route.

#### rules

List of IP routing rules.

On CentOS or Rocky, each item should be a string describing an iproute2 IP routing rule.

On Ubuntu, each item should be a dict containing optional items from, to, priority and table. from is the source address prefix to match with optional prefix. to is the destination address prefix to match with optional prefix. priority is the priority of the rule. table is the routing table ID.

#### physical\_network

Name of the physical network on which this network exists. This aligns with the physical network concept in neutron. This may be used to customise the Neutron physical network name used for an external network. This attribute should be set for all external networks or none.

#### libvirt network name

A name to give to a Libvirt network representing this network on the seed hypervisor.

### no\_ip

Whether to allocate an IP address for this network. If set to true, an IP address will not be allocated.

# **Configuring an IP Subnet**

An IP subnet may be configured by setting the cidr attribute for a network to the CIDR representation of the subnet.

To configure a network called example with the 10.0.0.0/24 IP subnet:

Listing 30: networks.yml

```
example_cidr: 10.0.0.0/24
```

## **Configuring an IP Gateway**

An IP gateway may be configured by setting the gateway attribute for a network to the IP address of the gateway.

To configure a network called example with a gateway at 10.0.0.1:

Listing 31: networks.yml

```
example_gateway: 10.0.0.1
```

This gateway will be configured on all hosts to which the network is mapped. Note that configuring multiple IP gateways on a single host will lead to unpredictable results.

# **Configuring an API Virtual IP Address**

A virtual IP (VIP) address may be configured for use by Kolla Ansible on the internal and external networks, on which the API services will be exposed. The variable will be passed through to the kolla\_internal\_vip\_address or kolla\_external\_vip\_address Kolla Ansible variable.

To configure a network called example with a VIP at 10.0.0.2:

Listing 32: networks.yml

```
example_vip_address: 10.0.0.2
```

# **Configuring an API Fully Qualified Domain Name**

A Fully Qualified Domain Name (FQDN) may be configured for use by Kolla Ansible on the internal and external networks, on which the API services will be exposed. The variable will be passed through to the kolla\_internal\_fqdn or kolla\_external\_fqdn Kolla Ansible variable.

To configure a network called example with an FQDN at api.example.com:

Listing 33: networks.yml

```
example_fqdn: api.example.com
```

# **Configuring Static IP Routes**

Static IP routes may be configured by setting the routes attribute for a network to a list of routes.

To configure a network called example with a single IP route to the 10.1.0.0/24 subnet via 10.0.0.1:

Listing 34: networks.yml

```
example_routes:
    - cidr: 10.1.0.0/24
     gateway: 10.0.0.1
```

These routes will be configured on all hosts to which the network is mapped.

If necessary, custom options may be added to the route:

Listing 35: networks.yml

```
example_routes:
    - cidr: 10.1.0.0/24
    gateway: 10.0.0.1
    options:
        - onlink
        - metric 400
```

Note that custom options are not currently supported on Ubuntu.

# Configuring a VLAN

A VLAN network may be configured by setting the vlan attribute for a network to the ID of the VLAN. To configure a network called example with VLAN ID 123:

Listing 36: networks.yml

```
example_vlan: 123
```

# **IP Address Allocation**

IP addresses are allocated automatically by Kayobe from the allocation pool defined by allocation\_pool\_start and allocation\_pool\_end. If these variables are undefined, the entire network is used, except for network and broadcast addresses. IP addresses are only allocated if the network cidr is set and DHCP is not used (see bootproto in *Per-host Network Configuration*). The allocated addresses are stored in \${KAYOBE\_CONFIG\_PATH}/network-allocation.yml using the global per-network attribute ips which maps Ansible inventory hostnames to allocated IPs.

If static IP address allocation is required, the IP allocation file network-allocation.yml may be manually populated with the required addresses.

# **Configuring Dynamic IP Address Allocation**

To configure a network called example with the 10.0.0.0/24 IP subnet and an allocation pool spanning from 10.0.0.4 to 10.0.0.254:

Listing 37: networks.yml

```
example_cidr: 10.0.0.0/24
example_allocation_pool_start: 10.0.0.4
example_allocation_pool_end: 10.0.0.254
```

### Note

This pool should not overlap with an inspection or neutron allocation pool on the same network.

# **Configuring Static IP Address Allocation**

To configure a network called example with statically allocated IP addresses for hosts host1 and host2:

Listing 38: network-allocation.yml

```
example_ips:
   host1: 10.0.0.1
   host2: 10.0.0.2
```

### **Advanced: Policy-Based Routing**

Policy-based routing can be useful in complex networking environments, particularly where asymmetric routes exist, and strict reverse path filtering is enabled.

# **Configuring IP Routing Tables**

Custom IP routing tables may be configured by setting the global variable network\_route\_tables in \${KAYOBE\_CONFIG\_PATH}/networks.yml to a list of route tables. These route tables will be added to /etc/iproute2/rt\_tables.

To configure a routing table called exampleroutetable with ID 1:

Listing 39: networks.yml

```
network_route_tables:
    - name: exampleroutetable
    id: 1
```

To configure route tables on specific hosts, use a host or group variables file.

# **Configuring IP Routing Policy Rules**

IP routing policy rules may be configured by setting the rules attribute for a network to a list of rules. Two formats are supported for defining rules: string format and dict format. String format rules are only supported on CentOS Stream and Rocky Linux systems.

#### **Dict format rules**

The dict format of a rule is a dictionary with optional items from, to, priority, and table. table should be the name of a route table defined in network\_route\_tables.

To configure a network called example with an IP routing policy rule to handle traffic from the subnet 10.1.0.0/24 using the routing table exampleroutetable:

Listing 40: networks.yml

```
example_rules:
    - from: 10.1.0.0/24
    table: exampleroutetable
```

These rules will be configured on all hosts to which the network is mapped.

### String format rules (CentOS Stream/Rocky Linux only)

The string format of a rule is the string which would be appended to ip rule <add|del> to create or delete the rule. Note that when using NetworkManager (the default since Zed and in Yoga when using Rocky Linux 9) the table must be specified by ID.

To configure a network called example with an IP routing policy rule to handle traffic from the subnet 10.1.0.0/24 using the routing table with ID 1:

Listing 41: networks.yml

```
example_rules:
    - from 10.1.0.0/24 table 1
```

These rules will be configured on all hosts to which the network is mapped.

# **Configuring IP Routes on Specific Tables**

A route may be added to a specific routing table by adding the name or ID of the table to a table attribute of the route:

To configure a network called example with a default route and a connected (local subnet) route to the subnet 10.1.0.0/24 on the table exampleroutetable:

Listing 42: networks.yml

```
example_routes:
- cidr: 0.0.0.0/0 (continues on next page)
```

(continued from previous page)

gateway: 10.1.0.1
table: exampleroutetable
- cidr: 10.1.0.0/24

table: exampleroutetable

# **Configuring Custom Neutron Physical Network Names**

By default, Kolla Ansible uses Neutron physical network names starting with physnet1 through to physnetN for each external network interface on a host.

Sometimes we may want to customise the physical network names used. This may be to allow for not all hosts having access to all physical networks, or to use more descriptive names.

For example, in an environment with a separate physical network for Ironic provisioning, controllers might have access to two physical networks, while compute nodes have access to one. We could have a situation where the controllers and computes use inconsistent physical network names. To avoid this, we can add physical\_network attributes to these networks. In the following example, the Ironic provisioning network is provision\_wl, and the external network is external.

Listing 43: \$KAYOBE\_CONFIG\_PATH/networks.yml

```
provision_wl_physical_network: physnet1
external_physical_network: physnet2
```

This ensures that compute nodes treat external as physnet2, even though it is the only physical network to which they are attached.

### **Per-host Network Configuration**

Some network attributes are specific to a hosts role in the system, and these are stored in \${KAYOBE\_CONFIG\_PATH}/inventory/group\_vars/<group>/network-interfaces. The following attributes are supported:

#### interface

The name of the network interface attached to the network.

# parent

The name of the parent interface, when configuring a VLAN interface using systemd-networkd syntax.

### bootproto

Boot protocol for the interface. Valid values are static and dhcp. The default is static. When set to dhcp, an external DHCP server must be provided.

#### defroute

Whether to set the interface as the default route. This attribute can be used to disable configuration of the default gateway by a specific interface. This is particularly useful to ignore a gateway address provided via DHCP. Should be set to a boolean value. The default is unset. This attribute is only supported on distributions of the Red Hat family.

#### bridge\_ports

For bridge interfaces, a list of names of network interfaces to add to the bridge.

# bridge\_stp

### Note

For Rocky Linux 9, the bridge\_stp attribute is set to false to preserve backwards compatibility with network scripts. This is because the Network Manager sets STP to true by default on bridges.

Enable or disable the Spanning Tree Protocol (STP) on this bridge. Should be set to a boolean value. The default is not set on Ubuntu systems.

### bond\_mode

For bond interfaces, the bonds mode, e.g. 802.3ad.

#### bond\_ad\_select

For bond interfaces, the 802.3ad aggregation selection logic to use. Valid values are stable (default selection logic if not configured), bandwidth or count.

#### bond\_slaves

For bond interfaces, a list of names of network interfaces to act as slaves for the bond.

#### bond\_miimon

For bond interfaces, the time in milliseconds between MII link monitoring.

#### bond\_updelay

For bond interfaces, the time in milliseconds to wait before declaring an interface up (should be multiple of bond\_miimon).

### bond\_downdelay

For bond interfaces, the time in milliseconds to wait before declaring an interface down (should be multiple of bond\_miimon).

# bond\_xmit\_hash\_policy

For bond interfaces, the xmit\_hash\_policy to use for the bond.

#### bond\_lacp\_rate

For bond interfaces, the lacp\_rate to use for the bond.

### ethtool\_opts

### Note

ethtool\_opts is not currently supported on Ubuntu.

Physical network interface options to apply with ethtool. When used on bond and bridge interfaces, settings apply to underlying interfaces. This should be a string of arguments passed to the ethtool utility, for example "-G \${DEVICE} rx 8192 tx 8192".

#### zone

#### Note

zone is not currently supported on Ubuntu.

The name of firewalld zone to be attached to network interface.

### **IP Addresses**

An interface will be assigned an IP address if the associated network has a cidr attribute. The IP address will be assigned from the range defined by the allocation\_pool\_start and allocation\_pool\_end attributes, if one has not been statically assigned in network-allocation.yml.

# **Configuring Ethernet Interfaces**

An Ethernet interface may be configured by setting the interface attribute for a network to the name of the Ethernet interface.

To configure a network called example with an Ethernet interface on eth0:

```
Listing 44: inventory/group_vars/<group>/
network-interfaces
```

```
example_interface: eth0
```

# Advanced: Configuring (Renaming) Ethernet Interfaces System Name

The name of the Ethernet interface may be explicitly configured by binding known MAC address of the specific interface to its name by setting the macaddress attribute for a network.

#### Warning

Supported only on Ubuntu/Debian operating systems.

To configure a network called example with known MAC address aa:bb:cc:dd:ee:ff and rename it from a system name (might be eth0, ens3, or any other name) to the lan0 (new name):

```
Listing 45: inventory/group_vars/<group>/ network-interfaces
```

```
example_interface: lan0
example_macaddress: "aa:bb:cc:dd:ee:ff"
```

# Warning

The network interface must be down before changing its name. See issue in the systemd project. So the configured node reboot might be required right after the seed host configure or overcloud host configure Kayobe commands.

# **Configuring Bridge Interfaces**

A Linux bridge interface may be configured by setting the interface attribute of a network to the name of the bridge interface, and the bridge\_ports attribute to a list of interfaces which will be added as member ports on the bridge.

To configure a network called **example** with a bridge interface on **breth1**, and a single port **eth1**:

Listing 46: inventory/group\_vars/<group>/ network-interfaces

```
example_interface: breth1
example_bridge_ports:
    - eth1
```

Bridge member ports may be Ethernet interfaces, bond interfaces, or VLAN interfaces. In the case of bond interfaces, the bond must be configured separately in addition to the bridge, as a different named network. In the case of VLAN interfaces, the underlying Ethernet interface must be configured separately in addition to the bridge, as a different named network.

### **Configuring Bond Interfaces**

A bonded interface may be configured by setting the interface attribute of a network to the name of the bonds master interface, and the bond\_slaves attribute to a list of interfaces which will be added as slaves to the master.

To configure a network called example with a bond with master interface bond0 and two slaves eth0 and eth1:

Listing 47: inventory/group\_vars/<group>/ network-interfaces

```
example_interface: bond0
example_bond_slaves:
   - eth0
   - eth1
```

Optionally, the bond mode and MII monitoring interval may also be configured:

Listing 48: inventory/group\_vars/<group>/
network-interfaces

```
example_bond_mode: 802.3ad
example_bond_miimon: 100
```

Bond slaves may be Ethernet interfaces, or VLAN interfaces. In the case of VLAN interfaces, underlying Ethernet interface must be configured separately in addition to the bond, as a different named network.

# **Configuring VLAN Interfaces**

A VLAN interface may be configured by setting the interface attribute of a network to the name of the VLAN interface. The interface name must normally be of the form cparent interface.<VLAN ID> to ensure compatibility with all supported host operating systems.

To configure a network called example with a VLAN interface with a parent interface of eth2 for VLAN 123:

Listing 49: inventory/group\_vars/<group>/ network-interfaces

```
example_interface: eth2.123
```

To keep the configuration DRY, reference the networks vlan attribute:

Listing 50: inventory/group\_vars/<group>/ network-interfaces

```
example_interface: "eth2.{{ example_vlan }}"
```

Alternatively, when using Ubuntu as a host operating system, VLAN interfaces can be named arbitrarily using syntax supported by systemd-networkd. In this case, a parent attribute must specify the underlying interface:

Listing 51: inventory/group\_vars/<group>/ network-interfaces

```
example_interface: "myvlan{{ example_vlan }}"
example_parent: "eth2"
```

Ethernet interfaces, bridges, and bond master interfaces may all be parents to a VLAN interface.

# **Bridges and VLANs**

Adding a VLAN interface to a bridge directly will allow tagged traffic for that VLAN to be forwarded by the bridge, whereas adding a VLAN interface to an Ethernet or bond interface that is a bridge member port will prevent tagged traffic for that VLAN being forwarded by the bridge.

For example, if you are bridging eth1 to breth1 and want to access VLAN 1234 as a tagged VLAN from the host, while still allowing Neutron to access traffic for that VLAN via Open vSwitch, your setup should look like this:

```
$ sudo brctl show
bridge name bridge id STP enabled interfaces
breth1 8000.56e6b95b4178 no p-breth1-phy
eth1

$ sudo ip addr show | grep 1234 | head -1
10: breth1.1234@breth1: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 qdisc
→noqueue state UP group default qlen 1000
```

#### It should **not** look like this:

```
$ sudo brctl show
bridge name bridge id STP enabled interfaces
breth1 8000.56e6b95b4178 no p-breth1-phy
eth1

$ sudo ip addr show | grep 1234 | head -1
10: eth1.1234@eth1: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 qdisc noqueue
→state UP group default qlen 1000
```

This second configuration may be desirable to prevent specific traffic, e.g. of the internal API network, from reaching Neutron.

# **Domain Name Service (DNS) Resolver Configuration**

Kayobe supports configuration of hosts DNS resolver via resolv.conf. DNS configuration should be added to dns.yml. For example:

Listing 52: dns.yml

```
resolv_nameservers:
- 8.8.8.8
- 8.8.4.4
resolv_domain: example.com
```

(continues on next page)

(continued from previous page)

#### resolv\_search:

kayobe.example.com

It is also possible to prevent kayobe from modifying resolv.conf by setting resolv\_is\_managed to false.

### **Network Role Configuration**

In order to provide flexibility in the systems network topology, Kayobe maps the named networks to logical network roles. A single named network may perform multiple roles, or even none at all. The available roles are:

### Overcloud admin network (admin\_oc\_net\_name)

Name of the network used to access the overcloud for admin purposes, e.g for remote SSH access.

# Overcloud out-of-band network (oob\_oc\_net\_name)

Name of the network used by the seed to access the out-of-band management controllers of the bare metal overcloud hosts.

### Overcloud provisioning network (provision\_oc\_net\_name)

Name of the network used by the seed to provision the bare metal overcloud hosts.

# Workload out-of-band network (oob\_wl\_net\_name)

Name of the network used by the overcloud hosts to access the out-of-band management controllers of the bare metal workload hosts.

### Workload provisioning network (provision\_wl\_net\_name)

Name of the network used by the overcloud hosts to provision the bare metal workload hosts.

### Workload cleaning network (cleaning\_net\_name)

Name of the network used by the overcloud hosts to clean the baremetal workload hosts.

#### Internal network (internal\_net\_name)

Name of the network used to expose the internal OpenStack API endpoints.

### Public network (public\_net\_name)

Name of the network used to expose the public OpenStack API endpoints.

### Tunnel network (tunnel\_net\_name)

Name of the network used by Neutron to carry tenant overlay network traffic.

# External networks (external\_net\_names, deprecated: external\_net\_name)

List of names of networks used to provide external network access via Neutron. If external\_net\_name is defined, external\_net\_names defaults to a list containing only that network.

### Storage network (storage\_net\_name)

Name of the network used to carry storage data traffic.

### Storage management network (storage\_mgmt\_net\_name)

Name of the network used to carry storage management traffic.

# Swift storage network (swift\_storage\_net\_name)

Name of the network used to carry Swift storage data traffic. Defaults to the storage network (storage\_net\_name).

# Swift storage replication network (swift\_storage\_replication\_net\_name)

Name of the network used to carry storage management traffic. Defaults to the storage management network (storage\_mgmt\_net\_name)

# Workload inspection network (inspection\_net\_name)

Name of the network used to perform hardware introspection on the bare metal workload hosts.

These roles are configured in \${KAYOBE\_CONFIG\_PATH}/networks.yml.

#### Warning

Changing external\_net\_names after initial deployment has a potential for creating network loops. Kayobe / Ansible will not clean up any items removed from this variable in the OVS. Any additional interfaces that map to network names from the list will be added to the bridge. Any previous entries that should be removed, must be deleted in OVS manually prior to applying changes via Kayobe in order to avoid creating a loop.

# **Configuring Network Roles**

To configure network roles in a system with two networks, example1 and example2:

Listing 53: networks.yml

```
admin_oc_net_name: example1
oob_oc_net_name: example1
provision_oc_net_name: example1
oob_wl_net_name: example2
provision_wl_net_name: example2
internal_net_name: example2
public_net_name: example2
tunnel_net_name: example2
external_net_names:
    - example2
storage_net_name: example2
storage_met_name: example2
swift_storage_net_name: example2
swift_replication_net_name: example2
inspection_net_name: example2
cleaning_net_name: example2
```

### **Overcloud Admin Network**

The admin network is intended to be used for remote access to the overcloud hosts. Kayobe will use the address assigned to the host on this network as the ansible\_host when executing playbooks. It is therefore a necessary requirement to configure this network.

By default Kayobe will use the overcloud provisioning network as the admin network. It is, however, possible to configure a separate network. To do so, you should override admin\_oc\_net\_name in your networking configuration.

If a separate network is configured, the following requirements should be taken into consideration:

• The admin network must be configured to use the same physical network interface as the provisioning network. This is because the PXE MAC address is used to lookup the interface for the cloud-init network configuration that occurs during bifrost provisioning of the overcloud.

# **Overcloud Provisioning Network**

If using a seed to inspect the bare metal overcloud hosts, it is necessary to define a DHCP allocation pool for the seeds ironic inspector DHCP server using the inspection\_allocation\_pool\_start and inspection\_allocation\_pool\_end attributes of the overcloud provisioning network.

### Note

This example assumes that the example network is mapped to provision\_oc\_net\_name.

To configure a network called example with an inspection allocation pool:

```
example_inspection_allocation_pool_start: 10.0.0.128
example_inspection_allocation_pool_end: 10.0.0.254
```

#### Note

This pool should not overlap with a kayobe allocation pool on the same network.

### **Workload Cleaning Network**

A separate cleaning network, which is used by the overcloud to clean baremetal workload (compute) hosts, may optionally be specified. Otherwise, the Workload Provisoning network is used. It is necessary to define an IP allocation pool for neutron using the neutron\_allocation\_pool\_start and neutron\_allocation\_pool\_end attributes of the cleaning network. This controls the IP addresses that are assigned to workload hosts during cleaning.

#### Note

This example assumes that the example network is mapped to cleaning\_net\_name.

To configure a network called example with a neutron provisioning allocation pool:

```
example_neutron_allocation_pool_start: 10.0.1.128
example_neutron_allocation_pool_end: 10.0.1.195
```

# Note

This pool should not overlap with a kayobe or inspection allocation pool on the same network.

### **Workload Provisioning Network**

If using the overcloud to provision bare metal workload (compute) hosts, it is necessary to define an IP allocation pool for the overclouds neutron provisioning network using the neutron\_allocation\_pool\_start and neutron\_allocation\_pool\_end attributes of the workload provisioning network.

#### Note

This example assumes that the example network is mapped to provision\_wl\_net\_name.

To configure a network called example with a neutron provisioning allocation pool:

```
example_neutron_allocation_pool_start: 10.0.1.128
example_neutron_allocation_pool_end: 10.0.1.195
```

### Note

This pool should not overlap with a kayobe or inspection allocation pool on the same network.

# **Workload Inspection Network**

If using the overcloud to inspect bare metal workload (compute) hosts, it is necessary to define a DHCP allocation pool for the overclouds ironic inspector DHCP server using the inspection\_allocation\_pool\_start and inspection\_allocation\_pool\_end attributes of the workload provisioning network.

#### Note

This example assumes that the example network is mapped to provision\_wl\_net\_name.

To configure a network called example with an inspection allocation pool:

```
example_inspection_allocation_pool_start: 10.0.1.196
example_inspection_allocation_pool_end: 10.0.1.254
```

### Note

This pool should not overlap with a kayobe or neutron allocation pool on the same network.

# **Neutron Networking**

#### Note

This assumes the use of the neutron openvswitch ML2 mechanism driver for control plane networking.

Certain modes of operation of neutron require layer 2 access to physical networks in the system. Hosts in the network group (by default, this is the same as the controllers group) run the neutron networking services (Open vSwitch agent, DHCP agent, L3 agent, metadata agent, etc.).

The kayobe network configuration must ensure that the neutron Open vSwitch bridges on the network hosts have access to the external network. If bare metal compute nodes are in use, then they must also have access to the workload provisioning network. This can be done by ensuring that the external and workload provisioning network interfaces are bridges. Kayobe will ensure connectivity between these Linux bridges and the neutron Open vSwitch bridges via a virtual Ethernet pair. See *Configuring Bridge Interfaces*.

### **Network to Host Mapping**

Networks are mapped to hosts using the variable network\_interfaces. Kayobes playbook group variables define some sensible defaults for this variable for hosts in the top level standard groups. These defaults are set using the network roles typically required by the group.

### Seed

By default, the seed is attached to the following networks:

- · overcloud admin network
- · overcloud out-of-band network
- · overcloud provisioning network

This list may be extended by setting seed\_extra\_network\_interfaces to a list of names of additional networks to attach. Alternatively, the list may be completely overridden by setting seed\_network\_interfaces. These variables are found in \${KAYOBE\_CONFIG\_PATH}/seed.yml.

### **Seed Hypervisor**

By default, the seed hypervisor is attached to the same networks as the seed.

This list may be extended by setting seed\_hypervisor\_extra\_network\_interfaces to a list of names of additional networks to attach. Alternatively, the list may be completely overridden by setting seed\_hypervisor\_network\_interfaces. These variables are found in \${KAYOBE\_CONFIG\_PATH}/ seed-hypervisor.yml.

#### Infra VMs

By default, infrastructure VMs are attached to the following network:

· overcloud admin network

This list may be extended by setting infra\_vm\_extra\_network\_interfaces to a list of names of additional networks to attach. Alternatively, the list may be completely overridden by setting infra\_vm\_network\_interfaces. These variables are found in \${KAYOBE\_CONFIG\_PATH}/infra-vms.yml.

#### **Controllers**

By default, controllers are attached to the following networks:

- · overcloud admin network
- workload (compute) out-of-band network
- workload (compute) provisioning network
- workload (compute) inspection network
- workload (compute) cleaning network
- internal network
- · storage network

In addition, if the controllers are also in the network group, they are attached to the following networks:

- · public network
- · external network
- · tunnel network

This list may be extended by setting controller\_extra\_network\_interfaces to a list of names of additional networks to attach. Alternatively, the list may be completely overridden by setting controller\_network\_interfaces. These variables are found in \${KAYOBE\_CONFIG\_PATH}/controllers.yml.

### **Network Hosts**

By default, controllers provide Neutron network services and load balancing. If separate network hosts are used (see *Example 1: Adding Network Hosts*), they are attached to the following networks:

- · overcloud admin network
- · internal network
- · storage network
- · public network
- · external network
- tunnel network

This list may be extended by setting controller\_network\_host\_extra\_network\_interfaces to a list of names of additional networks to attach. Alternatively, the list may be completely overridden by setting controller\_network\_host\_network\_interfaces. These variables are found in \${KAYOBE\_CONFIG\_PATH}/controllers.yml.

# **Monitoring Hosts**

By default, the monitoring hosts are attached to the same networks as the controllers when they are in the controllers group. If the monitoring hosts are not in the controllers group, they are attached to the following networks by default:

- · overcloud admin network
- · internal network
- · public network

This list may be extended by setting monitoring\_extra\_network\_interfaces to a list of names of additional networks to attach. Alternatively, the list may be completely overridden by setting monitoring\_network\_interfaces. These variables are found in \${KAYOBE\_CONFIG\_PATH}/monitoring.yml.

# **Storage Hosts**

By default, the storage hosts are attached to the following networks:

- · overcloud admin network
- internal network
- · storage network
- storage management network

In addition, if Swift is enabled, they can also be attached to the Swift management and replication networks.

### **Virtualised Compute Hosts**

By default, virtualised compute hosts are attached to the following networks:

- · overcloud admin network
- internal network
- storage network
- · tunnel network


This list may be extended by setting compute\_extra\_network\_interfaces to a list of names of additional networks to attach. Alternatively, the list may be completely overridden by setting compute\_network\_interfaces. These variables are found in \${KAYOBE\_CONFIG\_PATH}/compute.yml.

#### **Other Hosts**

If additional hosts are managed by kayobe, the networks to which these hosts are attached may be defined in a host or group variables file. See *Control Plane Service Placement* for further details.

# **Complete Example**

The following example combines the complete network configuration into a single system configuration. In our example cloud we have three networks: management, cloud and external:



The management network is used to access the servers BMCs and by the seed to inspect and provision the cloud hosts. The cloud network carries all internal control plane and storage traffic, and is used by the control plane to provision the bare metal compute hosts. Finally, the external network links the cloud to the outside world.

We could describe such a network as follows:

Listing 54: networks.yml

```
# Network role mappings.
oob_oc_net_name: management
provision_oc_net_name: management
oob_wl_net_name: management
provision_wl_net_name: cloud
internal_net_name: cloud
public_net_name: external
external_net_name: external
storage_net_name: cloud
storage_mgmt_net_name: cloud
inspection_net_name: cloud
# management network definition.
management_cidr: 10.0.0.0/24
management_allocation_pool_start: 10.0.0.1
management_allocation_pool_end: 10.0.0.127
management_inspection_allocation_pool_start: 10.0.0.128
management_inspection_allocation_pool_end: 10.0.0.254
# cloud network definition.
cloud_cidr: 10.0.1.0/24
cloud_allocation_pool_start: 10.0.1.1
cloud_allocation_pool_end: 10.0.1.127
cloud_inspection_allocation_pool_start: 10.0.1.128
cloud_inspection_allocation_pool_end: 10.0.1.195
cloud_neutron_allocation_pool_start: 10.0.1.196
cloud_neutron_allocation_pool_end: 10.0.1.254
# external network definition.
external_cidr: 10.0.3.0/24
external_allocation_pool_start: 10.0.3.1
external_allocation_pool_end: 10.0.3.127
external_neutron_allocation_pool_start: 10.0.3.128
external_neutron_allocation_pool_end: 10.0.3.254
external_routes:
   cidr: 10.0.4.0/24
    gateway: 10.0.3.1
```

We can map these networks to network interfaces on the seed and controller hosts:

```
Listing 55: inventory/group_vars/seed/network-interfaces
```

```
management_interface: eth0
```

Listing 56: inventory/group\_vars/controllers/network-interfaces

```
management_interface: eth0
cloud_interface: breth1
cloud_bridge_ports:
    eth1
external_interface: eth2
```

We have defined a bridge for the cloud network on the controllers as this will allow it to be plugged into a neutron Open vSwitch bridge.

Kayobe will allocate IP addresses for the hosts that it manages:

Listing 57: network-allocation.yml

```
management_ips:
    seed: 10.0.0.1
    control0: 10.0.0.2
    control1: 10.0.0.3
    control2: 10.0.0.4
    cloud_ips:
        control0: 10.0.1.1
        control1: 10.0.1.2
        control2: 10.0.1.3
    external_ips:
        control0: 10.0.3.1
        control1: 10.0.3.2
        control2: 10.0.3.3
```

Note that although this file does not need to be created manually, doing so allows for a predictable IP address mapping which may be desirable in some cases.

## **Routed Control Plane Networks**

This section describes configuration for routed control plane networks. This is an advanced concept and generally applies only to larger deployments that exceed the reasonable size of a broadcast domain.

# Concept

Kayobe currently supports the definition of various different networks - public, internal, tunnel, etc. These typically map to a VLAN or flat network, with an associated IP subnet. When a cloud exceeds the reasonable size of a single VLAN/subnet, or is physically distributed, this approach no longer works.

One way to resolve this is to have multiple subnets that map to a single logical network, and provide routing between them. This is a similar concept to Neutrons routed provider networks, but for the control plane networks.

#### Limitations

There are currently a few limitations to using routed control plane networks. Only the following networks have been tested:

- admin\_oc
- internal
- tunnel
- storage
- storage\_mgmt

Additionally, only compute nodes and storage nodes have been tested with routed control plane networks - controllers were always placed on the same set of networks during testing.

Bare metal provisioning (of the overcloud or baremetal compute) has not been tested with routed control plane networks, and would not be expected to work without taking additional steps.

# Configuration

The approach to configuring Kayobe for routed control plane networks is as follows:

- create groups in the inventory for the different sets of networks
- place hosts in the appropriate groups
- move vip\_address and fqdn network attributes to *global variables*
- move global network name configuration to group variables
- add new networks to configuration
- add network interface group variables

### **Example**

In this example, we initially have a number of different logical networks:

- public\_0
  - -10.0.0.0/24
  - VLAN 100
- internal\_0
  - -10.0.1.0/24
  - VLAN 101
- tunnel\_0
  - -10.0.2.0/24
  - VLAN 102
- storage\_0

- -10.0.3.0/24
- VLAN 103
- storage\_mgmt\_0
  - -10.0.4.0/24
  - VLAN 104

Initially the following hosts are connected to these networks:

- controllers[0:2]: public\_0, internal\_0, tunnel\_0, storage\_0
- compute[0:127]: internal\_0, tunnel\_0, storage\_0
- storage[0:63]: internal\_0, storage\_0, storage\_mgmt\_0

Now consider that we wish to add 128 compute nodes and 64 storage nodes. This would exceed size of the current subnets. We could increase the subnet sizes, but there are good reasons to keep broadcast domains reasonably small.

To resolve this, we can add some more networks:

- internal\_1
  - -10.1.1.0/24
  - VLAN 111
- tunnel\_1
  - -10.1.2.0/24
  - VLAN 112
- storage\_1
  - -10.1.3.0/24
  - VLAN 113
- storage\_mgmt\_1
  - -10.1.4.0/24
  - VLAN 114

The network must provide routes between the following networks:

- internal\_0 and internal\_1
- tunnel\_0 and tunnel\_1
- storage\_0 and storage\_1
- storage\_mgmt\_0 and storage\_mgmt\_1

Now we can connect the new hosts to these networks:

- compute[128:255]: internal\_1, tunnel\_1, storage\_1
- storage[64:127]: internal\_1, storage\_1, storage\_mgmt\_1

# **Inventory**

To model this change we could use an inventory such as the following:

Listing 58: inventory/hosts

#### Kolla API addresses

Remove all variables defining vip\_address or fqdn network attributes from networks.yml, and move the configuration to the API address variables in kolla.yml.

#### **Network names**

To move global network name configuration to group variables, the following variables should be commented out in networks.yml:

Listing 59: networks.yml

```
#admin_oc_net_name:
#internal_net_name:
#tunnel_net_name:
#storage_net_name:
#storage_mgmt_net_name:
```

Create group variable files in inventory/group\_vars/network-0 and inventory/group\_vars/ network-1:

Listing 60: inventory/group\_vars/network-0

```
admin_oc_net_name: internal_0
internal_net_name: internal_0
tunnel_net_name: tunnel_0
storage_net_name: storage_0
storage_mgmt_net_name: storage_mgmt_0
```

Listing 61: inventory/group\_vars/network-1

```
admin_oc_net_name: internal_1
internal_net_name: internal_1
tunnel_net_name: tunnel_1
storage_net_name: storage_1
storage_mgmt_net_name: storage_mgmt_1
```

### **Networks**

Now, ensure both sets of networks are defined in networks.yml. Static routes are added between the pairs of networks here, although these will depend on your routing configuration. Other network attributes may be necessary, we are including cidr, vlan and routes only here for brevity:

Listing 62: networks.yml

```
public_0_cidr: 10.0.0.0/24
public_0_vlan: 100
internal_0_cidr: 10.0.1.0/24
```

(continues on next page)

(continued from previous page)

```
internal_0_vlan: 101
internal_0_routes:
   cidr: "{{ internal_1_cidr }}"
    gateway: 10.0.1.1
internal_1_cidr: 10.1.1.0/24
internal_1_vlan: 111
internal_1_routes:
  - cidr: "{{ internal_0_cidr }}"
   gateway: 10.1.1.1
tunnel_0_cidr: 10.0.2.0/24
tunnel_0_vlan: 102
tunnel_0_routes:
  cidr: "{{ tunnel_1_cidr }}"
    gateway: 10.0.2.1
tunnel_1_cidr: 10.1.2.0/24
tunnel_1_vlan: 112
tunnel_1_routes:
   cidr: "{{ tunnel_0_cidr }}"
   gateway: 10.1.2.1
storage_0_cidr: 10.0.3.0/24
storage_0_vlan: 103
storage_0_routes:
   cidr: "{{ storage_1_cidr }}"
   gateway: 10.0.3.1
storage_1_cidr: 10.1.3.0/24
storage_1_vlan: 113
storage_1_routes:
  - cidr: "{{ storage_0_cidr }}"
   gateway: 10.1.3.1
storage_mgmt_0_cidr: 10.0.4.0/24
storage_mgmt_0_vlan: 104
storage_mgmt_0_routes:
  - cidr: "{{ storage_mgmt_1_cidr }}"
   gateway: 10.0.4.1
storage_mgmt_1_cidr: 10.1.4.0/24
storage_mgmt_1_vlan: 114
storage_mgmt_1_routes:
   cidr: "{{ storage_mgmt_0_cidr }}"
    gateway: 10.1.4.1
```

60

### **Network interfaces**

Since there are now differently named networks, the network interface variables are named differently. This means that we must provide a group variables file for each set of networks and each type of host. For example:

Listing 63: inventory/group\_vars/compute-network-0/
network-interfaces

```
internal_0_interface: eth0.101
tunnel_0_interface: eth0.102
storage_0_interface: eth0.103
```

Listing 64: inventory/group\_vars/compute-network-1/
network-interfaces

```
internal_1_interface: eth0.111
tunnel_1_interface: eth0.112
storage_1_interface: eth0.113
```

Listing 65: inventory/group\_vars/storage-network-0/network-interfaces

```
internal_0_interface: eth0.101
storage_0_interface: eth0.103
storage_mgmt_0_interface: eth0.104
```

Listing 66: inventory/group\_vars/storage-network-1/network-interfaces

```
internal_1_interface: eth0.111
storage_1_interface: eth0.113
storage_mgmt_1_interface: eth0.114
```

The normal interface configuration group variables files inventory/group\_vars/compute/network-interfaces and inventory/group\_vars/storage/network-interfaces should be removed.

Group variables for controller network interfaces may be placed in inventory/group\_vars/controllers/network-interfaces as normal.

## Alternative approach

There is an alternative approach which has not been tested, but may be of interest. Rather than having differently named networks (e.g. internal\_0 and internal\_1), it should be possible to use the same name everywhere (e.g. internal), but define the network attributes in group variables. This approach may be a little less verbose, and allows the same group variables file to set the network interfaces as normal (e.g. via internal\_interface).

### **Host Configuration**

This section covers configuration of hosts. It does not cover configuration or deployment of containers. Hosts that are configured by Kayobe include:

- Seed hypervisor (kayobe seed hypervisor host configure)
- Seed (kayobe seed host configure)
- Infra VMs (kayobe infra vm host configure)
- Overcloud (kayobe overcloud host configure)

Unless otherwise stated, all host configuration described here is applied to each of these types of host.

# See also

Ansible tags for limiting the scope of Kayobe commands are included under the relevant sections of this page (for more information see *Tags*).

# **Configuration Location**

Some host configuration options are set via global variables, and others have a variable for each type of host. The latter variables are included in the following files under \${KAYOBE\_CONFIG\_PATH}:

- seed-hypervisor.yml
- seed.yml
- compute.yml
- controller.yml
- infra-vms.yml
- monitoring.yml
- storage.yml

Note that any variable may be set on a per-host or per-group basis, by using inventory host or group variables - these delineations are for convenience.

#### **Paths**

Several directories are used by Kayobe on the remote hosts. There is a hierarchy of variables in \${KAYOBE\_CONFIG\_PATH}/globals.yml that can be used to control where these are located.

- base\_path (default /opt/kayobe/) sets the default base path for various directories.
- config\_path (default {{ base\_path }}/etc) is a path in which to store configuration files.
- image\_cache\_path (default {{ base\_path }}/images) is a path in which to cache downloaded or built images.
- source\_checkout\_path (default {{ base\_path }}/src) is a path into which to store clones of source code repositories.

• virtualenv\_path (default {{ base\_path }}/venvs) is a path in which to create Python virtual environments.

### **SSH Known Hosts**

#### tags:

ssh-known-host

While strictly this configuration is applied to the Ansible control host (localhost), it is applied during the host configure commands. The ansible\_host of each host is added as an SSH known host. This is typically the hosts IP address on the admin network (admin\_oc\_net\_name), as defined in \${KAYOBE\_CONFIG\_PATH}/network-allocation.yml (see IP Address Allocation).

# **Kayobe User Bootstrapping**

#### tags:

kayobe-ansible-user

Kayobe uses a user account defined by the kayobe\_ansible\_user variable (in \${KAYOBE\_CONFIG\_PATH}/globals.yml) for remote SSH access. By default, this is stack.

Typically, the image used to provision these hosts will not include this user account, so Kayobe performs a bootstrapping step to create it, as a different user. In cloud images, there is often a user named after the OS distro, e.g. centos, rocky or ubuntu. This user defaults to the os\_distribution variable, but may be set via the following variables:

- seed\_hypervisor\_bootstrap\_user
- seed\_bootstrap\_user
- infra\_vm\_bootstrap\_user
- compute\_bootstrap\_user
- controller\_bootstrap\_user
- monitoring\_bootstrap\_user
- storage\_bootstrap\_user

For example, to set the bootstrap user for controllers to example-user:

#### Listing 67: controllers.yml

```
controller_bootstrap_user: example-user
```

# **PyPI Mirror and proxy**

tags:

pip

Kayobe supports configuration of a PyPI mirror and/or proxy, via variables in \${KAYOBE\_CONFIG\_PATH}/pip.yml. Mirror functionality is enabled by setting the pip\_local\_mirror variable to true and proxy functionality is enabled by setting pip\_proxy variable to a proxy URL.

Kayobe will generate configuration for:

- pip to use the mirror and proxy
- easy\_install to use the mirror

for the list of users defined by pip\_applicable\_users (default kayobe\_ansible\_user and root), in addition to the user used for Kolla Ansible (kolla\_ansible\_user). The mirror URL is configured via pip\_index\_url, and pip\_trusted\_hosts is a list of trusted hosts, for which SSL verification will be disabled.

For example, to configure use of the test PyPI mirror at https://test.pypi.org/simple/:

### Listing 68: pip.yml

```
pip_local_mirror: true
pip_index_url: https://test.pypi.org/simple/
```

To configure use of the PyPI proxy:

Listing 69: pip.yml

```
pip_proxy: http://your_proxy_server:3128
```

#### **Kayobe Remote Virtual Environment**

tags:

```
kayobe-target-venv
```

By default, Ansible executes modules remotely using the system python interpreter, even if the Ansible control process is executed from within a virtual environment (unless the local connection plugin is used). This is not ideal if there are python dependencies that must be installed with isolation from the system python packages. Ansible can be configured to use a virtualenv by setting the host variable ansible\_python\_interpreter to a path to a python interpreter in an existing virtual environment.

If kayobe detects that ansible\_python\_interpreter is set and references a virtual environment, it will create the virtual environment if it does not exist. Typically this variable should be set via a group variable in the inventory for hosts in the seed, seed-hypervisor, and/or overcloud groups.

The default Kayobe configuration in the kayobe-config repository sets ansible\_python\_interpreter to {{ virtualenv\_path }}/kayobe/bin/python for the seed, seed-hypervisor, and overcloud groups.

### **Disk Wiping**

#### tags:

```
wipe-disks
```

Using hosts that may have stale data on their disks could affect the deployment of the cloud. This is not a configuration option, since it should only be performed once to avoid losing useful data. It is triggered by passing the --wipe-disks argument to the host configure commands.

## **Users and Groups**

#### tags:

users

Linux user accounts and groups can be configured using the users\_default variable in \${KAYOBE\_CONFIG\_PATH}/users.yml. The format of the list is that used by the users variable of the singleplatform-eng.users role. The following variables can be used to set the users for specific types of hosts:

- seed\_hypervisor\_users
- seed\_users
- infra\_vm\_users
- compute\_users
- controller\_users
- monitoring\_users
- storage\_users

In the following example, a single user named bob is created. A password hash has been generated via mkpasswd --method=sha-512. The user is added to the wheel group, and an SSH key is authorised. The SSH public key should be added to the Kayobe configuration.

# Listing 70: users.yml

### **DNF Package Repositories**

tags:

dnf

On CentOS and Rocky, Kayobe supports configuration of package repositories via DNF, via variables in \${KAYOBE\_CONFIG\_PATH}/dnf.yml.

# Configuration of dnf.conf

Global configuration of DNF is stored in /etc/dnf/dnf.conf, and options can be set via the dnf\_config variable. Options are added to the [main] section of the file. For example, to configure DNF to use a proxy server:

### Listing 71: dnf.yml

```
dnf_config:
   proxy: https://proxy.example.com
```

### **CentOS/Rocky and EPEL Mirrors**

CentOS/Rocky and EPEL mirrors can be enabled by setting dnf\_use\_local\_mirror to true. CentOS repository mirrors are configured via the following variables:

- dnf\_centos\_mirror\_host (default mirror.centos.org) is the mirror hostname.
- dnf\_centos\_mirror\_directory (default centos) is a directory on the mirror in which repositories may be accessed.

Rocky repository mirrors are configured via the following variables:

- dnf\_rocky\_mirror\_host (default dl.rockylinux.org) is the mirror hostname
- dnf\_rocky\_mirror\_directory (default pub/rocky) is a directory on the mirror in which repositories may be accessed.

EPEL repository mirrors are configured via the following variables:

- dnf\_epel\_mirror\_host (default download.fedoraproject.org) is the mirror hostname.
- dnf\_epel\_mirror\_directory (default pub/epel) is a directory on the mirror in which repositories may be accessed.

For example, to configure CentOS and EPEL mirrors at mirror.example.com:

#### Listing 72: dnf.yml

```
dnf_use_local_mirror: true
dnf_centos_mirror_host: mirror.example.com
dnf_epel_mirror_host: mirror.example.com
```

### **Custom DNF Repositories**

It is also possible to configure a list of custom DNF repositories via the dnf\_custom\_repos variable. The format is a dict/map, with repository names mapping to a dict/map of arguments to pass to the Ansible yum\_repository module.

For example, the following configuration defines a single DNF repository called widgets.

### Listing 73: dnf.yml

```
dnf_custom_repos:
    widgets:
        baseurl: http://example.com/repo
        file: widgets
        gpgkey: http://example.com/gpgkey
        gpgcheck: yes
```

# **Enabling or disabling EPEL**

Prior to the Yoga release, the EPEL DNF repository was enabled by default (dnf\_install\_epel: true). Since Yoga, it is disabled by default (dnf\_install\_epel: false).

Previously, EPEL was required to install some packages such as python-pip, however this is no longer the case.

It is possible to enable or disable the EPEL DNF repository by setting dnf\_install\_epel to true or false respectively.

#### **DNF Automatic**

DNF Automatic provides a mechanism for applying regular updates of packages. DNF Automatic is disabled by default, and may be enabled by setting dnf\_automatic\_enabled to true.

Listing 74: dnf.yml

```
dnf_automatic_enabled: true
```

By default, only security updates are applied. Updates for all packages may be installed by setting dnf\_automatic\_upgrade\_type to default. This may cause the system to be less predictable as packages are updated without oversight or testing.

### **Apt**

tags:

apt

On Ubuntu, Apt is used to manage packages and package repositories.

# Apt cache

The Apt cache timeout may be configured via apt\_cache\_valid\_time (in seconds) in etc/kayobe/apt.yml, and defaults to 3600.

### Apt proxy

Apt can be configured to use a proxy via apt\_proxy\_http and apt\_proxy\_https in etc/kayobe/apt.yml. These should be set to the full URL of the relevant proxy (e.g. http://squid.example.com:3128).

### **Apt configuration**

Arbitrary global configuration options for Apt may be defined via the apt\_config variable in etc/kayobe/apt.yml since the Yoga release. The format is a list, with each item mapping to a dict/map with the following items:

- content: free-form configuration file content
- filename: name of a file in /etc/apt/apt.conf.d/ in which to write the configuration

The default of apt\_config is an empty list.

For example, the following configuration tells Apt to use 2 attempts when downloading packages:

Listing 75: apt.yml

```
apt_config:
    - content: |
        Acquire::Retries 1;
    filename: 99retries
```

# **Apt repositories**

Kayobe supports configuration of custom Apt repositories via the apt\_repositories variable in etc/kayobe/apt.yml since the Yoga release. The format is a list, with each item mapping to a dict/map with the following items:

- types: whitespace-separated list of repository types, e.g. deb or deb-src (optional, default is deb)
- url: URL of the repository
- suites: whitespace-separated list of suites, e.g. noble (optional, default is ansible\_facts. distribution\_release)
- components: whitespace-separated list of components, e.g. main (optional, default is main)
- signed\_by: whitespace-separated list of names of GPG keyring files in apt\_keys\_path (optional, default is unset)
- architecture: whitespace-separated list of architectures that will be used (optional, default is unset)

• trusted: boolean value (optional, default is unset)

The default of apt\_repositories is an empty list.

For example, the following configuration defines a single Apt repository:

Listing 76: apt.yml

```
apt_repositories:
    types: deb
    url: https://example.com/repo
    suites: noble
    components: all
```

In the following example, the Ubuntu Noble 24.04 repositories are consumed from a local package mirror. The apt\_disable\_sources\_list variable is set to true, which disables all repositories in /etc/apt/sources.list, including the default Ubuntu ones.

### Listing 77: apt.yml

```
apt_repositories:
    - url: http://mirror.example.com/ubuntu/
        suites: noble noble-updates
        components: main restricted universe multiverse
        - url: http://mirror.example.com/ubuntu/
        suites: noble-security
        components: main restricted universe multiverse

apt_disable_sources_list: true
```

#### Apt keys

Some repositories may be signed by a key that is not one of Apts trusted keys. Kayobe avoids the use of the deprecated apt-key utility, and instead allows keys to be downloaded to a directory. This enables repositories to use the SignedBy option to state that they are signed by a specific key. This approach is more secure than using globally trusted keys.

Keys to be downloaded are defined by the apt\_keys variable. The format is a list, with each item mapping to a dict/map with the following items:

- url: URL of key
- filename: Name of a file in which to store the downloaded key in apt\_keys\_path. The extension should be .asc for ASCII-armoured keys, or .gpg otherwise.

The default value of apt\_keys is an empty list.

In the following example, a key is downloaded, and a repository is configured that is signed by the key.

Listing 78: apt.yml

(continued from previous page)

```
apt_repositories:
    types: deb
    url: https://example.com/repo
    suites: noble
    components: all
    signed_by: example-key.asc
```

### **Apt preferences**

Arbitrary global preferences options for Apt may be defined via the apt\_preferences variable in etc/kayobe/apt.yml. The format is a list, with each item mapping to a dict/map with the following items:

- content: free-form preferences file content
- filename: name of a file in /etc/apt/preferences.d/ in which to write the configuration

The default of apt\_preferences is an empty list.

For example, the following configuration tells Apt to only pin a specific package from a custom repo, while preventing installing any other packages from there:

Listing 79: apt.yml

```
apt_preferences:
    - content: |
        Package: *
        Pin: origin your.custom.repo
        Pin-Priority: 1

        Package: specific-package
        Pin: origin your.custom.repo
        Pin-Priority: 500
        filename: 99-pin-custom-repo
```

### Apt auth configuration

Some repositories may require authentication using HTTP basic auth. Apt supports specifying credentials in URLs in sources.list files, but these files must be world-readable. A more secure setup involves writing credentials to auth.conf files which can have more restrictive permissions.

Auth configuration is defined by the apt\_auth variable. The format is a list, with each item mapping to a dict/map with the following items:

- machine: machine entry in the auth file
- login: machine entry in the auth file
- password: machine entry in the auth file
- filename: Name of a file in /etc/apt/auth.conf.d in which to store the auth configuration. The extension should be .conf.

The default value of apt\_auth is an empty list.

In the following example, credentials are provided for package repositories at apt.example.com.

# Listing 80: apt.yml

```
apt_auth:
    - machine: apt.example.com
    login: my-username
    password: my-password
    filename: example.conf
```

### **Development tools**

tags:

dev-tools

Development tools (additional OS packages) can be configured to be installed on hosts. By default Ddvelopment tools are installed on all seed-hypervisor, seed, overcloud and infra-vms hosts.

The following variables can be used to set which packages to install:

- dev\_tools\_packages\_default: The list of packages installed by default. (default is: bash-completion, tcpdump and vim)
- dev\_tools\_packages\_extra: The list of additional packages installed alongside default packages. (default is an empty list)

In the following example, the list of default packages to be installed on all hosts is modified to replace vim with emacs. The bridge-utils package is added to all overcloud hosts:

Listing 81: dev-tools.yml

Listing 82: inventory/group\_vars/overcloud/dev-tools

```
dev_tools_packages_extra:
    - bridge-utils
```

#### **SELinux**

tags:

selinux

## Note

SELinux applies to CentOS and Rocky systems only.

SELinux is not supported by Kolla Ansible currently, so it is set to permissive by Kayobe. If necessary, it can be configured to disabled by setting selinux\_state to disabled. Kayobe will reboot systems when required for the SELinux configuration. The timeout for waiting for systems to reboot is selinux\_reboot\_timeout. Alternatively, the reboot may be avoided by setting selinux\_do\_reboot to false.

# **Network Configuration**

#### tags:

network

Configuration of host networking is covered in depth in Network Configuration.

#### **Firewalld**

#### tags:

firewall

Firewalld can be used to provide a firewall on supported systems. Since the Xena release, Kayobe provides support for enabling or disabling firewalld, as well as defining zones and rules. Since the Zed 13.0.0 release, Kayobe added support for configuring firewalld on Ubuntu systems.

The following variables can be used to set whether to enable firewalld:

- seed\_hypervisor\_firewalld\_enabled
- seed\_firewalld\_enabled
- infra\_vm\_firewalld\_enabled
- compute\_firewalld\_enabled
- controller\_firewalld\_enabled
- monitoring\_firewalld\_enabled
- storage\_firewalld\_enabled

When firewalld is enabled, the following variables can be used to configure a list of zones to create. Each item is a dict containing a zone item:

- seed\_hypervisor\_firewalld\_zones
- seed\_firewalld\_zones
- infra\_vm\_firewalld\_zones
- compute\_firewalld\_zones
- controller\_firewalld\_zones
- monitoring\_firewalld\_zones
- storage\_firewalld\_zones

The following variables can be used to set a default zone. The default is unset, in which case the default zone will not be changed:

- seed\_hypervisor\_firewalld\_default\_zone
- seed\_firewalld\_default\_zone
- infra\_vm\_firewalld\_default\_zone
- compute\_firewalld\_default\_zone
- controller\_firewalld\_default\_zone
- monitoring\_firewalld\_default\_zone
- storage\_firewalld\_default\_zone

The following variables can be used to set a list of rules to apply. Each item is a dict containing arguments to pass to the firewalld module. Arguments are omitted if not provided, with the following exceptions: offline (default true), permanent (default true), state (default enabled):

- seed\_hypervisor\_firewalld\_rules
- seed\_firewalld\_rules
- infra\_vm\_firewalld\_rules
- compute\_firewalld\_rules
- controller\_firewalld\_rules
- monitoring\_firewalld\_rules
- storage\_firewalld\_rules

In the following example, firewalld is enabled on controllers. public and internal zones are created, with their default rules disabled. TCP port 8080 is open in the internal zone, and the http service is open in the public zone:

```
controller_firewalld_enabled: true
controller_firewalld_zones:
   zone: public
    zone: internal
controller_firewalld_rules:
  # Disable default rules in internal zone.
   service: dhcpv6-client
    state: disabled
    zone: internal
   service: samba-client
    state: disabled
   zone: internal
   service: ssh
   state: disabled
    zone: internal
  # Disable default rules in public zone.
   service: dhcpv6-client
    state: disabled
    zone: public
    service: ssh
```

(continues on next page)

(continued from previous page)

```
state: disabled
zone: public

# Enable TCP port 8080 in internal zone.
- port: 8080/tcp
zone: internal
# Enable the HTTP service in the public zone.
- service: http
zone: public
```

### **UFW**

tags:

firewall

Configuration of Uncomplicated Firewall (UFW) on Ubuntu hosts is currently not supported. Instead, UFW is disabled. Since Yoga, this may be avoided as follows:

```
ufw_enabled: true
```

Note that despite the name, this will not actively enable UFW. It may do so in the future.

#### **Tuned**

tags:

tuned

#### Note

Tuned configuration only supports CentOS/Rocky systems for now.

Built-in tuned profiles can be applied to hosts. The following variables can be used to set a tuned profile to specific types of hosts:

- seed\_hypervisor\_tuned\_active\_builtin\_profile
- seed\_tuned\_active\_builtin\_profile
- compute\_tuned\_active\_builtin\_profile
- controller\_tuned\_active\_builtin\_profile
- monitoring\_tuned\_active\_builtin\_profile
- storage\_tuned\_active\_builtin\_profile
- infra\_vm\_tuned\_active\_builtin\_profile

By default, Kayobe applies a tuned profile matching the role of each host in the system:

- seed hypervisor: virtual-host
- seed: virtual-guest

• infrastructure VM: virtual-guest

• compute: virtual-host

• controllers: throughput-performance

• monitoring: throughput-performance

• storage: throughput-performance

For example, to change the tuned profile of controllers to network-throughput:

Listing 83: controllers.yml

```
controller_tuned_active_builtin_profile: network-throughput
```

### **Sysctls**

#### tags:

sysctl

Arbitrary sysctl configuration can be applied to hosts. The variable format is a dict/map, mapping parameter names to their required values. The following variables can be used to set sysctl configuration specific types of hosts:

- seed\_hypervisor\_sysctl\_parameters
- seed\_sysctl\_parameters
- infra\_vm\_sysctl\_parameters
- compute\_sysctl\_parameters
- controller\_sysctl\_parameters
- monitoring\_sysctl\_parameters
- storage\_sysctl\_parameters

For example, to set the net.ipv4.ip\_forward parameter to 1 on controllers:

Listing 84: controllers.yml

```
controller_sysctl_parameters:
  net.ipv4.ip_forward: 1
```

# **IP routing and Source NAT**

#### tags:

```
ip-routing
snat
```

IP routing and source NAT (SNAT) can be configured on the seed host, which allows it to be used as a default gateway for overcloud hosts. This is disabled by default since the Xena 11.0.0 release, and may be enabled by setting seed\_enable\_snat to true in \${KAYOBE\_CONFIG\_PATH}/seed.yml.

The seed-hypervisor host also can be configured the same way to be used as a default gateway. This is disabled by default too, and may be enabled by setting seed\_hypervisor\_enable\_snat to true in \${KAYOBE\_CONFIG\_PATH}/seed-hypervisor.yml.

#### Disable cloud-init

tags:

disable-cloud-init

cloud-init is a popular service for performing system bootstrapping. If you are not using cloud-init, this section can be skipped.

If using the seeds Bifrost service to provision the control plane hosts, the use of cloud-init may be configured via the kolla\_bifrost\_dib\_init\_element variable.

cloud-init searches for network configuration in order of increasing precedence; each item overriding the previous. In some cases, on subsequent boots cloud-init can automatically reconfigure network interfaces and cause some issues in network configuration. To disable cloud-init from running after the initial server bootstrapping, set disable\_cloud\_init to true in \${KAYOBE\_CONFIG\_PATH}/overcloud.yml.

### **Disable Glean**

tags:

disable-glean

The glean service can be used to perform system bootstrapping, serving a similar role to cloud-init. If you are not using glean, this section can be skipped.

If using the seeds Bifrost service to provision the control plane hosts, the use of glean may be configured via the kolla\_bifrost\_dib\_init\_element variable.

After the initial server bootstrapping, the glean service can cause problems as it attempts to enable all network interfaces, which can lead to timeouts while booting. To avoid this, the glean service is disabled. Additionally, any network interface configuration files generated by glean and not overwritten by Kayobe are removed.

#### **Timezone**

tags:

timezone

The timezone can be configured via the timezone variable in \${KAYOBE\_CONFIG\_PATH}/time.yml. The value must be a valid Linux timezone. For example:

Listing 85: time.yml

timezone: Europe/London

#### **NTP**

tags:

ntp

Kayobe will configure Chrony on all hosts in the ntp group. The default hosts in this group are:

```
[ntp:children]
# Kayobe will configure Chrony on members of this group.
seed
seed-hypervisor
overcloud
```

This provides a flexible way to opt in or out of having kayobe manage the NTP service.

#### **Variables**

Network Time Protocol (NTP) may be configured via variables in \${KAYOBE\_CONFIG\_PATH}/time. yml. The list of NTP servers is configured via chrony\_ntp\_servers, and by default the pool.ntp.org servers are used.

Internally, kayobe uses the mrlesmithjr.chrony Ansible role. Rather than maintain a mapping between the kayobe and mrlesmithjr.chrony worlds, all variables are simply passed through. This means you can use all variables that the role defines. For example to change chrony\_maxupdateskew and override the kayobe defaults for chrony\_ntp\_servers:

Listing 86: time.yml

```
chrony_ntp_servers:
    - server: 0.debian.pool.ntp.org
    options:
        - option: iburst
        - option: minpoll
        val: 8
chrony_maxupdateskew: 150.0
```

# **Software RAID**

tags:

mdadm

While it is possible to use RAID directly with LVM, some operators may prefer the userspace tools provided by mdadm or may have existing software RAID arrays they want to manage with Kayobe.

Software RAID arrays may be configured via the mdadm\_arrays variable. For convenience, this is mapped to the following variables:

- seed\_hypervisor\_mdadm\_arrays
- seed\_mdadm\_arrays
- infra\_vm\_mdadm\_arrays

- compute\_mdadm\_arrays
- controller\_mdadm\_arrays
- monitoring\_mdadm\_arrays
- storage\_mdadm\_arrays

The format of these variables is as defined by the mdadm\_arrays variable of the mrlesmithjr.mdadm Ansible role.

For example, to configure two of the seeds disks as a RAID1 mdadm array available as /dev/md0:

Listing 87: seed.yml

# **Encryption**

#### tags:

luks

Encrypted block devices may be configured via the luks\_devices variable. For convenience, this is mapped to the following variables:

- seed\_hypervisor\_luks\_devices
- seed\_luks\_devices
- infra\_vm\_luks\_devices
- compute\_luks\_devices
- controller\_luks\_devices
- monitoring\_luks\_devices
- storage\_luks\_devices

The format of these variables is as defined by the luks\_devices variable of the stackhpc.luks Ansible role.

For example, to encrypt the software raid device, /dev/md0, on the seed, and make it available as /dev/mapper/md0crypt

Listing 88: seed.yml

```
seed_luks_devices:
    - name: md0crypt
    device: /dev/md0
```

#### Note

It is not yet possible to encrypt the root device.

### **LVM**

### tags:

1 vm

Logical Volume Manager (LVM) physical volumes, volume groups, and logical volumes may be configured via the lvm\_groups variable. For convenience, this is mapped to the following variables:

- seed\_hypervisor\_lvm\_groups
- seed\_lvm\_groups
- infra\_vm\_lvm\_groups
- compute\_lvm\_groups
- controller\_lvm\_groups
- monitoring\_lvm\_groups
- storage\_lvm\_groups

The format of these variables is as defined by the lvm\_groups variable of the mrlesmithjr.manage\_lvm Ansible role.

#### **LVM** for libvirt

LVM is not configured by default on the seed hypervisor. It is possible to configure LVM to provide storage for a libvirt storage pool, typically mounted at /var/lib/libvirt/images.

To use this configuration, set the seed\_hypervisor\_lvm\_groups variable to "{{ seed\_hypervisor\_lvm\_groups\_with\_data }}" and provide a list of disks via the seed\_hypervisor\_lvm\_group\_data\_disks variable.

### **LVM for Docker**

#### Note

In Train and earlier releases of Kayobe, the data volume group was always enabled by default.

A logical volume for storing Docker volume data, mounted at /var/lib/docker/volumes can optionally be created. The logical volume is created in volume group called data.

This configuration is enabled by the following variables, which default to false:

- compute\_lvm\_group\_data\_enabled
- controller\_lvm\_group\_data\_enabled

- seed\_lvm\_group\_data\_enabled
- infra\_vm\_lvm\_group\_data\_enabled
- storage\_lvm\_group\_data\_enabled

To use this configuration, a list of disks must be configured via the following variables:

- seed\_lvm\_group\_data\_disks
- infra\_vm\_lvm\_group\_data\_disks
- compute\_lvm\_group\_data\_disks
- controller\_lvm\_group\_data\_disks
- monitoring\_lvm\_group\_data\_disks
- storage\_lvm\_group\_data\_disks

For example, to configure two of the seeds disks for use by LVM:

Listing 89: seed.yml

# seed\_lvm\_group\_data\_disks:

- /dev/sdb
- /dev/sdc

The Docker volumes LVM volume is assigned a size given by the following variables, with a default value of 75% (of the volume groups capacity):

- seed\_lvm\_group\_data\_lv\_docker\_volumes\_size
- infra\_vm\_lvm\_group\_data\_lv\_docker\_volumes\_size
- compute\_lvm\_group\_data\_lv\_docker\_volumes\_size
- controller\_lvm\_group\_data\_lv\_docker\_volumes\_size
- monitoring\_lvm\_group\_data\_lv\_docker\_volumes\_size
- storage\_lvm\_group\_data\_lv\_docker\_volumes\_size

You can control the amount of storage assigned to the docker volumes LV by using the following variable.

Listing 90: controllers.yml

```
controller_lvm_group_data_lv_docker_volumes_size: 100%
```

It is possible to avoid using LVM entirely, thus avoiding the requirement for multiple disks. In this case, set the appropriate <host>\_lvm\_groups variable to an empty list:

# Listing 91: storage.yml

```
storage_lvm_groups: []
```

#### **Custom LVM**

To define additional logical volumes in the default data volume group, modify one of the following variables:

- seed\_lvm\_group\_data\_lvs
- infra\_vm\_lvm\_group\_data\_lvs
- compute\_lvm\_group\_data\_lvs
- controller\_lvm\_group\_data\_lvs
- monitoring\_lvm\_group\_data\_lvs
- storage\_lvm\_group\_data\_lvs

Include the variable <host>\_lvm\_group\_data\_lv\_docker\_volumes in the list to include the LVM volume for Docker volume data:

### Listing 92: monitoring.yml

```
monitoring_lvm_group_data_lvs:
    - "{{ monitoring_lvm_group_data_lv_docker_volumes }}"
    - lvname: other-vol
    size: 1%
    create: true
    filesystem: ext4
    mount: true
    mntp: /path/to/mount
```

It is possible to define additional LVM volume groups via the following variables:

- seed\_lvm\_groups\_extra
- infra\_vm\_lvm\_groups\_extra
- compute\_lvm\_groups\_extra
- controller\_lvm\_groups\_extra
- monitoring\_lvm\_groups\_extra
- storage\_lvm\_groups\_extra

For example:

Listing 93: compute.yml

```
compute_lvm_groups_extra:
    - vgname: other-vg
    disks:
```

(continues on next page)

(continued from previous page)

```
- /dev/sdb
create: true
lvnames:
    - lvname: other-vol
    size: 100%FREE
    create: true
    mount: false
```

Alternatively, replace the entire volume group list via one of the <host>\_lvm\_groups variables to replace the default configuration with a custom one.

Listing 94: controllers.yml

### **Kolla-Ansible Remote Virtual Environment**

### tags:

```
kolla-ansible kolla-target-venv
```

See *Context: Remote Execution Environment* for information about remote Python virtual environments for Kolla Ansible.

### **Docker Engine**

# tags:

docker

The docker\_storage\_driver variable sets the Docker storage driver, and by default the overlay2 driver is used. See *LVM* for information about configuring LVM for Docker.

If using an insecure (HTTP) registry, set docker\_registry\_insecure to true.

A private Docker registry may be configured via docker\_registry, with a Certificate Authority (CA) file configured via docker\_registry\_ca.

To use one or more Docker Registry mirrors, use the docker\_registry\_mirrors variable.

If using an MTU other than 1500, docker\_daemon\_mtu can be used to configure this. This setting does not apply to containers using net=host (as Kolla Ansibles containers do), but may be necessary when building images.

Dockers live restore feature can be configured via docker\_daemon\_live\_restore, although it is disabled by default due to issues observed.

# **Compute libvirt daemon**

#### tags:

libvirt-host

#### Note

This section is about the libvirt daemon on compute nodes, as opposed to the seed hypervisor.

Since Yoga, Kayobe provides support for deploying and configuring a libvirt host daemon, as an alternative to the nova\_libvirt container support by Kolla Ansible. The host daemon is not used by default, but it is possible to enable it by setting kolla\_enable\_nova\_libvirt\_container to false in \$KAYOBE\_CONFIG\_PATH/kolla.yml.

Migration of hosts from a containerised libvirt to host libvirt is currently not supported.

The following options are available in \$KAYOBE\_CONFIG\_PATH/compute.yml and are relevant only when using the libvirt daemon rather than the nova\_libvirt container:

#### compute\_libvirt\_enabled

Whether to enable a host libvirt daemon. Default is true if kolla\_enable\_nova is true and kolla\_enable\_nova\_libvirt\_container is false.

# compute\_libvirt\_conf\_default

A dict of default configuration options to write to /etc/libvirt/libvirtd.conf.

#### compute\_libvirt\_conf\_extra

A dict of additional configuration options to write to /etc/libvirt/libvirtd.conf.

# compute\_libvirt\_conf

A dict of configuration options to write to /etc/libvirt/libvirtd.conf. Default is a combination of compute\_libvirt\_conf\_default and compute\_libvirt\_conf\_extra.

### compute\_libvirtd\_log\_level

Numerical log level for libvirtd. Default is 3.

#### compute\_qemu\_conf\_default

A dict of default configuration options to write to /etc/libvirt/qemu.conf.

## compute\_qemu\_conf\_extra

A dict of additional configuration options to write to /etc/libvirt/qemu.conf.

#### compute\_qemu\_conf

A dict of configuration options to write to /etc/libvirt/qemu.conf. Default is a combination of compute\_qemu\_conf\_default and compute\_qemu\_conf\_extra.

#### compute\_libvirt\_enable\_sasl

Whether to enable libvirt SASL authentication. Default is the same as compute\_libvirt\_tcp\_listen.

# compute\_libvirt\_sasl\_password

libvirt SASL password. Default is unset. This must be defined when compute\_libvirt\_enable\_sasl is true.

# compute\_libvirt\_enable\_tls

Whether to enable a libvirt TLS listener. Default is false.

# compute\_libvirt\_ceph\_repo\_install

Whether to install a Ceph package repository on CentOS and Rocky hosts. Default is true.

### compute\_libvirt\_ceph\_repo\_release

Ceph package repository release to install on CentOS and Rocky hosts when compute\_libvirt\_ceph\_repo\_install is true. Default is pacific.

# **Example: custom libvirtd.conf**

To customise the libvirt daemon log output to send level 3 to the journal:

## Listing 95: compute.yml

```
compute_libvirt_conf_extra:
  log_outputs: "3:journald"
```

# Example: custom qemu.conf

To customise QEMU to avoid adding timestamps to logs:

### Listing 96: compute.yml

```
compute_qemu_conf_extra:
  log_timestamp: 0
```

### **Example: SASL**

SASL authentication is enabled by default. This provides authentication for TCP and TLS connections to the libvirt API. A password is required, and should be encrypted using Ansible Vault.

### Listing 97: compute.yml

```
compute_libvirt_sasl_password: !vault |
$ANSIBLE_VAULT; 1.1; AES256

→63363937303539373738356236393563636466313130633435353933613637343231303836343933

→3463623265653030323665383337376462363434396361320a653737376237353261303066616537

→666613562316533313632613433643537346463303363376664396661343835373033326261383065

→3731643633656636360a62353431366534306665616133388666133383132666134653363323764633234
```

### **Example: enabling libvirt TLS listener**

To enable the libvirt TLS listener:

Listing 98: compute.yml

```
compute_libvirt_enable_tls: true
```

When the TLS listener is enabled, it is necessary to provide client, server and CA certificates. The following files should be provided:

#### cacert.pem

CA certificate used to sign client and server certificates.

### clientcert.pem

Client certificate.

#### clientkey.pem

Client key.

### servercert.pem

Server certificate.

# serverkey.pem

Server key.

It is recommended to encrypt the key files using Ansible Vault.

The following paths are searched for these files:

- \$KAYOBE\_CONFIG\_PATH/certificates/libvirt/{{ inventory\_hostname }}/
- \$KAYOBE\_CONFIG\_PATH/certificates/libvirt/

In this way, certificates may be generated for each host, or shared using wildcard certificates.

If using Kayobe environments, certificates in the environment take precedence.

Kayobe makes the CA certificate and client certificate and key available to Kolla Ansible, for use by the nova\_compute service.

# **Example: disabling Ceph repository installation**

On CentOS and Rocky hosts, a CentOS Storage SIG Ceph repository is installed that provides more recent Ceph libraries than those available in CentOS/Rocky AppStream. This may be necessary when using Ceph for Cinder volumes or Nova ephemeral block devices. In some cases, such as when using local package mirrors, the upstream repository may not be appropriate. The installation of the repository may be disabled as follows:

# Listing 99: compute.yml

compute\_libvirt\_ceph\_repo\_install: false

## **Example: installing additional packages**

In some cases it may be useful to install additional packages on compute hosts for use by libvirt. The stackhpc.libvirt-host Ansible role supports this via the libvirt\_host\_extra\_daemon\_packages variable. The variable should be defined via group variables in the Ansible inventory, to avoid applying the change to the seed hypervisor. For example, to install the trousers package used for accessing TPM hardware:

Listing 100: inventory/group\_vars/compute/libvirt

```
libvirt_host_extra_daemon_packages:
```

- trousers

# **Swap**

# tags:

swap

Swap files and devices may be configured via the swap variable. For convenience, this is mapped to the following variables:

- seed\_swap
- seed\_hypervisor\_swap
- infra\_vm\_swap
- compute\_swap
- controller\_swap
- monitoring\_swap
- storage\_swap

The format is a list, with each item mapping to a dict/map. For a swap device, the following item should be present:

• device: Absolute path to a swap device.

For a swap file, the following items should be present:

- path: Absolute path to a swap file to create.
- size\_mb: Size of the swap file in MiB.

The default value of swap is an empty list.

# Example: enabling swap using a swap partition

The following example defines a swap device using an existing /dev/sda3 partition on controller hosts:

Listing 101: controllers.yml

```
controller_swap:
    - device: /dev/sda3
```

# Example: enabling swap using a swap file

The following example defines a 1GiB swap file that will be created at /swapfile on compute hosts:

Listing 102: compute.yml

```
compute_swap:
    path: /swapfile
    size_mb: 1024
```

# **AppArmor for the libvirt container**

tags:

apparmor-libvirt

#### Note

Prior to the Yoga release, this was handled by the kolla-ansible bootstrap-servers command.

On Ubuntu systems running the nova\_libvirt Kolla container, AppArmor rules for libvirt are disabled.

# Adding entries to /etc/hosts

tags:

etc-hosts

#### Note

Prior to the Yoga release, this was handled by the kolla-ansible bootstrap-servers command.

Since Yoga, Kayobe adds entries to /etc/hosts for all hosts in the overcloud group. The entries map the hostname and FQDN of a host to its IP address on the internal API network. This may be avoided as follows:

```
customize_etc_hosts: false
```

By default, each host gets an entry for every other host in the overcloud group by default. The list of hosts that will be added may be customised:

```
etc_hosts_hosts: "{{ groups['compute'] }}"
```

It should be noted that this functionality requires facts to be populated for all hosts that will be added to any /etc/hosts file. When using the --limit argument, Kayobe will gather facts for all hosts without facts, including those outside of the limit. Enabling fact caching for Kayobe may reduce the impact of this. This fact gathering process may be avoided as follows:

```
etc_hosts_gather_facts: false
```

# Installing packages required by Kolla Ansible

tags:

kolla-packages

#### Note

Prior to the Yoga release, this was handled by the kolla-ansible bootstrap-servers command.

A small number of packages are required to be installed on the hosts for Kolla Ansible and the services that it deploys, while some others must be removed.

# Logging

tags:

logging

Kayobe will configure persistent logging for nodes in the following ansible groups:

- · seed-hypervisor
- · seed
- · overcloud
- infra-vms

This means that the systemd journal will be written to local storage (instead of to memory) and will allow you to view the journal from previous boots. The storage limit defaults to 10% of the filesystem with a 4GiB hard limit (when using journald defaults). See journald documentation for more details.

Should you wish to disable this feature, you can set journald\_storage to volatile.

### **Kolla Configuration**

Anyone using Kayobe to build images should familiarise themselves with the Kolla projects documentation.

# **Container Image Build Host**

Images are built on hosts in the container-image-builders group. The default Kayobe Ansible inventory places the seed host in this group, although it is possible to put a different host in the group, by modifying the inventory.

For example, to build images on localhost:

### Listing 103: inventory/groups

[container-image-builders:children]

# Listing 104: inventory/hosts

[container-image-builders]
localhost

### **Kolla Installation**

Prior to building container images, Kolla and its dependencies will be installed on the container image build host. The following variables affect the installation of Kolla:

#### kolla\_ctl\_install\_type

Type of installation, either binary (PyPI) or source (git). Default is source.

#### kolla source path

Path to directory for Kolla source code checkout. Default is  $\{\{ \text{ source\_checkout\_path } \sim '/ \text{kolla' } \}\}$ .

# kolla\_source\_url

URL of Kolla source code repository if type is source. Default is https://opendev.org/openstack/kolla.

#### kolla\_source\_version

Version (branch, tag, etc.) of Kolla source code repository if type is source. Default is {{ openstack\_branch }}, which is the same as the Kayobe upstream branch name.

### kolla\_venv

Path to virtualenv in which to install Kolla on the container image build host. Default is {{ virtualenv\_path ~ '/kolla' }}.

### kolla\_build\_config\_path

Path in which to generate kolla configuration. Default is {{ config\_path ~ '/kolla' }}.

For example, to install from a custom Git repository:

# Listing 105: kolla.yml

```
kolla_source_url: https://git.example.com/kolla
kolla_source_version: downstream
```

# **Global Configuration**

The following variables are global, affecting all container images. They are used to generate the Kolla configuration file, kolla-build.conf, and also affect *Kolla Ansible configuration*.

### kolla\_base\_arch

Kolla base container image architecture. Options are x86\_64, aarch64. Default is {{ ansible\_facts.architecture }}.

#### kolla base distro

Kolla base container image distribution. Options are centos, debian, rocky or ubuntu. Default is {{ os\_distribution }}.

#### kolla\_base\_distro\_version

 $Kolla\ base\ container\ image\ distribution\ version.\ Default\ is\ dependent\ on\ kolla\_base\_distro.$ 

### kolla\_docker\_namespace

Docker namespace to use for Kolla images. Default is kolla.

### kolla\_docker\_registry

URL of docker registry to use for Kolla images. Default is to use the value of docker\_registry variable (see *Docker Engine*).

#### kolla\_docker\_registry\_username

Username to use to access a docker registry. Default is not set, in which case the registry will be used without authentication.

### kolla\_docker\_registry\_password

Password to use to access a docker registry. Default is not set, in which case the registry will be used without authentication.

### kolla\_openstack\_release

Kolla OpenStack release version. This should be a Docker image tag. Default is the OpenStack release name (e.g. rocky) on stable branches and tagged releases, or master on the Kayobe master branch.

#### kolla\_tag

Kolla container image tag. This is the tag that will be applied to built container images. Default is kolla\_openstack\_release.

For example, to build the Kolla rocky images with a namespace of example, and a private Docker registry at registry.example.com:4000, using the zed release:

# Listing 106: kolla.yml

```
kolla_base_distro: rocky
kolla_docker_namespace: example
kolla_docker_registry: registry.example.com:4000
kolla_openstack_release: zed
```

The ironic-api image built with this configuration would be referenced as follows:

```
registry.example.com:4000/example/ironic-api:zed-rocky-9
```

Further customisation of the Kolla configuration file can be performed by writing a file at \${KAYOBE\_CONFIG\_PATH/kolla/kolla-build.conf. For example, to enable debug logging:

Listing 107: kolla/kolla-build.conf

```
[DEFAULT]
debug = True
```

# **Seed Images**

The kayobe seed container image build command builds images for the seed services. The only image required for the seed services is the bifrost-deploy image.

# **Overcloud Images**

The kayobe overcloud container image build command builds images for the control plane. The default set of images built depends on which services and features are enabled via the kolla\_enable\_<service> flags in \$KAYOBE\_CONFIG\_PATH/kolla.yml.

For example, the following configuration will enable the Magnum service and add the magnum-api and magnum-conductor containers to the set of overcloud images that will be built:

Listing 108: kolla.yml

```
kolla_enable_magnum: true
```

If a required image is not built when the corresponding flag is set, check the image sets defined in overcloud\_container\_image\_sets in ansible/inventory/group\_vars/all/kolla.

# **Image Customisation**

There are three main approaches to customising the Kolla container images:

- 1. Overriding Jinja2 blocks
- 2. Overriding Jinja2 variables
- 3. Source code locations

# **Overriding Jinja2 blocks**

Kollas images are defined via Jinja2 templates that generate Dockerfiles. Jinja2 blocks are frequently used to allow specific statements in one or more Dockerfiles to be replaced with custom statements. See the Kolla documentation for details.

Blocks are configured via the kolla\_build\_blocks variable, which is a dict mapping Jinja2 block names in to their contents.

For example, to override the block header to add a custom label to every image:

Listing 109: kolla.yml

```
kolla_build_blocks:
header: |
LABEL foo="bar"
```

This will result in Kayobe generating a template-override. j2 file with the following content:

### Listing 110: template-override.j2

```
{% extends parent_template %}

{% block header %}

LABEL foo="bar"
{% endblock %}
```

### **Overriding Jinja2 variables**

Jinja2 variables offer another way to customise images. See the Kolla documentation for details of using variable overrides to modify the list of packages to install in an image.

Variable overrides are configured via the kolla\_build\_customizations variable, which is a dict/map mapping names of variables to override to their values.

For example, to add mod\_auth\_openidc to the list of packages installed in the keystone-base image, we can set the variable keystone\_base\_packages\_append to a list containing mod\_auth\_openidc.

Listing 111: kolla.yml

```
kolla_build_customizations:
    keystone_base_packages_append:
    - mod_auth_openidc
```

This will result in Kayobe generating a template-override. j2 file with the following content:

# Listing 112: template-override.j2

```
{% extends parent_template %}
{% set keystone_base_packages_append = ["mod_auth_openidc"] %}
```

Note that the variable value will be JSON-encoded in template-override.j2.

### Source code locations

For source image builds, configuration of source code locations for packages installed in containers by Kolla is possible via the kolla\_sources variable. The format is a dict/map mapping names of sources to their definitions. See the Kolla documentation for details. The default is to specify the URL and version of Bifrost, as defined in \${KAYOBE\_CONFIG\_PATH}/bifrost.yml.

For example, to specify a custom source location for the ironic-base package:

Listing 113: kolla.yml

```
kolla_sources:
  bifrost-base:
    type: "git"
    location: "{{ kolla_bifrost_source_url }}"
    reference: "{{ kolla_bifrost_source_version }}"
    ironic-base:
        type: "git"
    location: https://git.example.com/ironic
    reference: downstream
```

This will result in Kayobe adding the following configuration to kolla-build.conf:

Listing 114: kolla-build.conf

```
[bifrost-base]
type = git
location = https://opendev.org/openstack/bifrost
reference = stable/rocky

[ironic-base]
type = git
location = https://git.example.com/ironic
reference = downstream
```

Note that it is currently necessary to include the Bifrost source location if using a seed.

### Plugins & additions

These features can also be used for installing plugins and additions to source type images.

For example, to install a networking-ansible plugin in the neutron-server image:

Listing 115: kolla.yml

```
kolla_sources:
    bifrost-base:
        type: "git"
        location: "{{        kolla_bifrost_source_url }}"
        reference: "{{        kolla_bifrost_source_version }}"
        neutron-server-plugin-networking-ansible:
            type: "git"
```

(continues on next page)

(continued from previous page)

```
location: https://git.example.com/networking-ansible
reference: downstream
```

The neutron-server image automatically installs any plugins provided to it. For images that do not, a block such as the following may be required:

Listing 116: kolla.yml

```
kolla_build_blocks:
   neutron_server_footer: |
   ADD plugins-archive /
   pip --no-cache-dir install /plugins/*
```

A similar approach may be used for additions.

# **Kolla Ansible Configuration**

Kayobe relies heavily on Kolla Ansible for deployment of the OpenStack control plane. Kolla Ansible is installed locally on the Ansible control host (the host from which Kayobe commands are executed), and Kolla Ansible commands are executed from there.

Kolla Ansible configuration is stored in \${KAYOBE\_CONFIG\_PATH}/kolla.yml.

# **Configuration of Ansible**

Ansible configuration is described in detail in the Ansible documentation. In addition to the standard locations, Kayobe supports using an Ansible configuration file located in the Kayobe configuration at \${KAYOBE\_CONFIG\_PATH}/kolla/ansible.cfg or \${KAYOBE\_CONFIG\_PATH}/ansible.cfg. Note that if the ANSIBLE\_CONFIG environment variable is specified it takes precedence over this file.

#### **Kolla Ansible Installation**

Prior to deploying containers, Kolla Ansible and its dependencies will be installed on the Ansible control host. The following variables affect the installation of Kolla Ansible:

# kolla\_ansible\_ctl\_install\_type

Type of Kolla Ansible control installation. One of binary (PyPI) or source (git). Default is source.

# kolla\_ansible\_source\_url

URL of Kolla Ansible source code repository if type is source. Default is https://opendev.org/openstack/kolla-ansible.

#### kolla\_ansible\_source\_version

Version (branch, tag, etc.) of Kolla Ansible source code repository if type is source. Default is the same as the Kayobe upstream branch.

# kolla\_ansible\_venv\_extra\_requirements

Extra requirements to install inside the Kolla Ansible virtualenv. Default is an empty list.

### kolla\_upper\_constraints\_file

Upper constraints file for installation of Kolla. Default is {{ pip\_upper\_constraints\_file }}, which has a default of https://releases.openstack.org/constraints/upper/{{ openstack\_branch }}.

# **Example: custom git repository**

To install Kolla Ansible from a custom git repository:

#### Listing 117: \$KAYOBE\_CONFIG\_PATH/kolla.yml

```
kolla_ansible_source_url: https://git.example.com/kolla-ansible
kolla_ansible_source_version: downstream
```

### **Virtual Environment Extra Requirements**

Extra Python packages can be installed inside the Kolla Ansible virtualenv, such as when required by Ansible plugins.

For example, to use the hashi\_vault Ansible lookup plugin, its hvac dependency can be installed using:

## Listing 118: \$KAYOBE\_CONFIG\_PATH/kolla.yml

```
# Extra requirements to install inside the Kolla Ansible virtualenv.

kolla_ansible_venv_extra_requirements:
- "hvac"
```

### **Local environment**

The following variables affect the local environment on the Ansible control host. They reference environment variables, and should be configured using those rather than modifying the Ansible variable directly. The file kayobe-env in the kayobe-config git repository sets some sensible defaults for these variables, based on the recommended environment directory structure.

# kolla\_ansible\_source\_path

Path to directory for Kolla Ansible source code checkout. Default is \$KOLLA\_SOURCE\_PATH, or \$PWD/src/kolla-ansible.

# kolla\_ansible\_venv

Path to virtualenv in which to install Kolla Ansible on the Ansible control host. Default is \$KOLLA\_VENV\_PATH or \$PWD/venvs/kolla-ansible.

# kolla\_config\_path

Path to Kolla Ansible configuration directory. Default is \$KOLLA\_CONFIG\_PATH or /etc/kolla.

# **Global Configuration**

The following variables are global, affecting all containers. They are used to generate the Kolla Ansible configuration file, globals.yml, and also affect *Kolla image build configuration*.

# **Kolla Images**

The following variables affect which Kolla images are used, and how they are accessed.

### kolla\_base\_distro

Kolla base container image distribution. Default is {{ os\_distribution }}.

### kolla\_base\_distro\_version

Kolla base container image distribution version. Default is dependent on kolla\_base\_distro.

# kolla\_docker\_registry

URL of docker registry to use for Kolla images. Default is not set, in which case Quay.io will be used.

### kolla\_docker\_namespace

Docker namespace to use for Kolla images. Default is kolla.

# kolla\_docker\_registry\_username

Username to use to access a docker registry. Default is not set, in which case the registry will be used without authentication.

# kolla\_docker\_registry\_password

Password to use to access a docker registry. Default is not set, in which case the registry will be used without authentication.

### kolla\_openstack\_release

Kolla OpenStack release version. This should be a Docker image tag. Default is {{ openstack\_release }}, which takes the OpenStack release name (e.g. rocky) on stable branches and tagged releases, or master on the Kayobe master branch.

For example, to deploy Kolla rocky images with a namespace of example, and a private Docker registry at registry.example.com: 4000, and the zed release.

### Listing 119: \$KAYOBE\_CONFIG\_PATH/kolla.yml

```
kolla_base_distro: rocky
kolla_docker_namespace: example
kolla_docker_registry: registry.example.com:4000
kolla_openstack_release: zed
```

## The deployed ironic-api image would be referenced as follows:

```
registry.example.com:4000/example/ironic-api:zed-rocky-9
```

#### **Ansible**

The following variables affect how Ansible accesses the remote hosts.

# kolla\_ansible\_user

User account to use for Kolla SSH access. Default is kolla.

#### kolla\_ansible\_group

Primary group of Kolla SSH user. Default is kolla.

### kolla\_ansible\_become

Whether to use privilege escalation for all operations performed via Kolla Ansible. Default is false since the 8.0.0 Ussuri release.

### kolla\_ansible\_target\_venv

Path to a virtual environment on remote hosts to use for Ansible module execution. Default is {{ virtualenv\_path }}/kolla-ansible. May be set to None to use the system Python interpreter.

#### **Context: Remote Execution Environment**

By default, Ansible executes modules remotely using the system python interpreter, even if the Ansible control process is executed from within a virtual environment (unless the local connection plugin is used). This is not ideal if there are python dependencies that must be installed with isolation from the system python packages. Ansible can be configured to use a virtualenv by setting the host variable ansible\_python\_interpreter to a path to a python interpreter in an existing virtual environment.

The variable kolla\_ansible\_target\_venv configures the use of a virtual environment on the remote hosts. The default configuration should work in most cases.

#### **User account creation**

Since the Ussuri release, Kayobe creates a user account for Kolla Ansible rather than this being done during Kolla Ansibles bootstrap-servers command. This workflow is more compatible with Ansible fact caching, but does mean that Kolla Ansibles create\_kolla\_user variable cannot be used to disable creation of the user account. Instead, set kolla\_ansible\_create\_user to false.

# kolla\_ansible\_create\_user

Whether to create a user account, configure passwordless sudo and authorise an SSH key for Kolla Ansible. Default is true.

# **OpenStack Logging**

The following variable affects OpenStack debug logging.

### kolla\_openstack\_logging\_debug

Whether debug logging is enabled for OpenStack services. Default is false.

# Example: enabling debug logging

In certain situations it may be necessary to enable debug logging for all OpenStack services. This is not usually advisable in production.

Listing 120: \$KAYOBE\_CONFIG\_PATH/kolla.yml

\_\_\_

kolla\_openstack\_logging\_debug: true

#### **API Addresses**

#### Note

These variables should be used over the deprecated vip\_address and fqdn network attributes.

The following variables affect the addresses used for the external and internal API.

### kolla\_internal\_vip\_address

Virtual IP address of OpenStack internal API. Default is the vip\_address attribute of the internal network.

### kolla\_internal\_fqdn

Fully Qualified Domain Name (FQDN) of OpenStack internal API. Default is the fqdn attribute of the internal network if set, otherwise kolla\_internal\_vip\_address.

### kolla\_external\_vip\_address

Virtual IP address of OpenStack external API. Default is the vip\_address attribute of the external network.

### kolla\_external\_fqdn

Fully Qualified Domain Name (FQDN) of OpenStack external API. Default is the fqdn attribute of the external network if set, otherwise kolla\_external\_vip\_address.

# **TLS Encryption of APIs**

The following variables affect TLS encryption of the public API.

#### kolla\_enable\_tls\_external

Whether TLS is enabled for the public API endpoints. Default is no.

#### kolla\_external\_tls\_cert

A TLS certificate bundle to use for the public API endpoints, if kolla\_enable\_tls\_external is true. Note that this should be formatted as a literal style block scalar.

The following variables affect TLS encryption of the internal API. Currently this requires all Kolla images to be built with the APIs root CA trusted.

# kolla\_enable\_tls\_internal

Whether TLS is enabled for the internal API endpoints. Default is no.

#### kolla\_internal\_tls\_cert

A TLS certificate bundle to use for the internal API endpoints, if kolla\_enable\_tls\_internal is true. Note that this should be formatted as a literal style block scalar.

The following variables affect the generated admin-openrc.sh and public-openrc.sh environment files.

### kolla\_public\_openrc\_cacert

Path to a CA certificate file to use for the OS\_CACERT environment variable in the public-openrc.sh file when TLS is enabled, instead of kolla\_admin\_openrc\_cacert.

## kolla\_admin\_openrc\_cacert

Path to a CA certificate file to use for the OS\_CACERT environment variable in the admin-openrc. sh and public-openrc.sh files when TLS is enabled, instead of Kolla Ansibles default.

### **Example: enabling TLS for the public API**

It is highly recommended to use TLS encryption to secure the public API. Here is an example:

Listing 121: \$KAYOBE\_CONFIG\_PATH/kolla.yml

```
kolla_enable_tls_external: yes
kolla_external_tls_cert: |
    ----BEGIN CERTIFICATE----
    ...
    ----END CERTIFICATE----
kolla_admin_openrc_cacert: /path/to/ca/certificate/bundle
```

# **Example: enabling TLS for the internal API**

It is highly recommended to use TLS encryption to secure the internal API. Here is an example:

Listing 122: \$KAYOBE\_CONFIG\_PATH/kolla.yml

```
kolla_enable_tls_internal: yes
kolla_internal_tls_cert: |
    ----BEGIN CERTIFICATE----
    ...
    ----END CERTIFICATE----
kolla_admin_openrc_cacert: /path/to/ca/certificate/bundle
```

## Other certificates

In general, Kolla Ansible expects certificates to be in a directory configured via kolla\_certificates\_dir, which defaults to a directory named certificates in the same directory as globals.yml. Kayobe follows this pattern, and will pass files and directories added to \${KAYOBE\_CONFIG\_PATH}/kolla/certificates/ through to Kolla Ansible. This can be useful when enabling backend API TLS encryption, or providing custom CA certificates to be added to the trust store in containers. It is also possible to use this path to provide certificate bundles for the external or internal APIs, as an alternative to kolla\_external\_tls\_cert and kolla\_internal\_tls\_cert.

Note that Ansible will automatically decrypt these files if they are encrypted via Ansible Vault and it has access to a Vault password.

### **Example: adding a trusted custom CA certificate to containers**

In an environment with a private CA, it may be necessary to add the root CA certificate to the trust store of containers.

Listing 123: \$KAYOBE\_CONFIG\_PATH

```
kolla/
certificates/
ca/
private-ca.crt
```

These files should be PEM-formatted, and have a .crt extension.

# **Example: adding certificates for backend TLS**

Kolla Ansible backend TLS can be used to provide end-to-end encryption of API traffic.

Listing 124: \$KAYOBE\_CONFIG\_PATH

```
kolla/
certificates/
backend-cert.pem
backend-key.pem
```

See the Kolla Ansible documentation for how to provide service and/or host-specific certificates and keys.

### **Custom Global Variables**

Kolla Ansible uses a single file for global variables, globals.yml. Kayobe provides configuration variables for all required variables and many of the most commonly used the variables in this file. Some of these are in \$KAYOBE\_CONFIG\_PATH/kolla.yml, and others are determined from other sources such as the networking configuration in \$KAYOBE\_CONFIG\_PATH/networks.yml.

Additional global configuration may be provided by creating \$KAYOBE\_CONFIG\_PATH/kolla/globals.yml. Variables in this file will be templated using Jinja2, and merged with the Kayobe globals.yml configuration.

### Example: use a specific tag for each image

For more fine-grained control over images, Kolla Ansible allows a tag to be defined for each image. For example, for nova-api:

Listing 125: \$KAYOBE\_CONFIG\_PATH/kolla/globals.yml

```
# Use a custom tag for the nova-api container image.
nova_api_tag: v1.2.3
```

### Example: debug logging per-service

Enabling debug logging globally can lead to a lot of additional logs being generated. Often we are only interested in a particular service. For example, to enable debug logging for Nova services:

Listing 126: \$KAYOBE\_CONFIG\_PATH/kolla/globals.yml

```
nova_logging_debug: true
```

#### Host variables

Kayobe generates a host\_vars file for each host in the Kolla Ansible inventory. These contain network interfaces and other host-specific things. Some Kayobe Ansible variables are passed through to Kolla Ansible, as defined by the following variables. The default set of variables should typically be kept. Additional variables may be passed through via the \*\_extra variables, as described below. If a passed through variable is not defined for a host, it is ignored.

### kolla\_seed\_inventory\_pass\_through\_host\_vars

List of names of host variables to pass through from kayobe hosts to the Kolla Ansible seed host, if set. See also kolla\_seed\_inventory\_pass\_through\_host\_vars\_map. The default is:

```
kolla_seed_inventory_pass_through_host_vars:
    "ansible_host"
    "ansible_port"
    "ansible_ssh_private_key_file"
    "kolla_api_interface"
    "kolla_bifrost_network_interface"
```

It is possible to extend this list via kolla\_seed\_inventory\_pass\_through\_host\_vars\_extra.

# kolla\_seed\_inventory\_pass\_through\_host\_vars\_map

Dict mapping names of variables in kolla\_seed\_inventory\_pass\_through\_host\_vars to the variable to use in Kolla Ansible. If a variable name is not in this mapping the kayobe name is used. The default is:

```
kolla_seed_inventory_pass_through_host_vars_map:
   kolla_api_interface: "api_interface"
   kolla_bifrost_network_interface: "bifrost_network_interface"
```

It is possible to extend this dict via kolla\_seed\_inventory\_pass\_through\_host\_vars\_map\_extra.

#### kolla\_overcloud\_inventory\_pass\_through\_host\_vars

List of names of host variables to pass through from Kayobe hosts to Kolla Ansible hosts, if set. See also kolla\_overcloud\_inventory\_pass\_through\_host\_vars\_map. The default is:

```
kolla_overcloud_inventory_pass_through_host_vars
   "ansible_host"
   "ansible_port"
  - "ansible_ssh_private_key_file"
   "kolla_network_interface"
  "kolla_api_interface"
   "kolla_storage_interface"
  "kolla_cluster_interface"
   "kolla_swift_storage_interface"
   "kolla_swift_replication_interface"
   "kolla_provision_interface"
   "kolla_inspector_dnsmasq_interface"
   "kolla_dns_interface"
   "kolla_tunnel_interface"
   "kolla_external_vip_interface"
    "kolla_neutron_external_interfaces"
```

(continues on next page)

(continued from previous page)

```
- "kolla_neutron_bridge_names"
- "kolla_neutron_physical_networks"
```

It is possible to extend this list via kolla\_overcloud\_inventory\_pass\_through\_host\_vars\_extra.

# kolla\_overcloud\_inventory\_pass\_through\_host\_vars\_map

Dict mapping names of variables in kolla\_overcloud\_inventory\_pass\_through\_host\_vars to the variable to use in Kolla Ansible. If a variable name is not in this mapping the Kayobe name is used. The default is:

```
kolla_network_interface: "network_interface"
kolla_api_interface: "api_interface"
kolla_storage_interface: "storage_interface"
kolla_cluster_interface: "cluster_interface"
kolla_swift_storage_interface: "swift_storage_interface"
kolla_swift_replication_interface: "swift_replication_interface"
kolla_provision_interface: "provision_interface"
kolla_inspector_dnsmasq_interface: "ironic_dnsmasq_interface"
kolla_dns_interface: "dns_interface"
kolla_tunnel_interface: "tunnel_interface"
kolla_neutron_external_interfaces: "neutron_external_interface"
kolla_neutron_bridge_names: "neutron_physical_networks"
```

It is possible to extend this dict via  $kolla\_overcloud\_inventory\_pass\_through\_host\_vars\_map\_extra$ .

## Example: pass through an additional host variable

In this example we pass through a variable named my\_kayobe\_var from Kayobe to Kolla Ansible.

Listing 127: \$KAYOBE\_CONFIG\_PATH/kolla.yml

This variable might be defined in the Kayobe inventory, e.g.

Listing 128: \$KAYOBE\_CONFIG\_PATH/inventory/host\_vars/
controller01

```
my_kayobe_var: foo
```

The variable may then be referenced in \$KAYOBE\_CONFIG\_PATH/kolla/globals.yml, Kolla Ansible group variables, or in Kolla Ansible custom service configuration.

In case the variable requires a different name in Kolla Ansible, use kolla\_overcloud\_inventory\_pass\_through\_host\_vars\_map\_extra:

#### Listing 129: \$KAYOBE\_CONFIG\_PATH/kolla.yml

```
kolla_overcloud_inventory_pass_through_host_vars_map_extra:
   my_kayobe_var: my_kolla_ansible_var
```

# **Custom Kolla Inventory**

When running Kolla Ansible playbooks, kayobe will check for any customised inventories in the following locations:

- \${KAYOBE\_CONFIG\_PATH}/kolla/inventory/
- \${KAYOBE\_CONFIG\_PATH}/environments/<environment>/kolla/inventory/
  - Only used with the *multiple environments feature*

These are copied when kayobe generates the Kolla Ansible configuration. The copy is passed to Ansible as an additional inventory when running any Kolla Ansible playbooks. No templating or additional preprocessing is performed. For this reason, this directory must be a valid Ansible inventory, with the exception that \*.j2 files are ignored to keep compatibility with *custom Kolla Ansible inventory templates*.

Group variables can be used to set configuration for all hosts in a group. They can be set in Kolla Ansible by placing files in \${KAYOBE\_CONFIG\_PATH}/kolla/inventory/group\_vars/\*. Since this directory is copied directly into the Kolla Ansible inventory, Kolla Ansible group names should be used. It should be noted that extra-vars and host\_vars take precedence over group\_vars. For more information on variable precedence see the Ansible documentation.

### **Example: configure a Nova cell**

In Kolla Ansible, Nova cells are configured via group variables. For example, to configure cell0001 the following file could be created:

```
Listing 130: $KAYOBE_CONFIG_PATH/kolla/inventory/group_vars/cell0001/all
```

```
nova_cell_name: cell0001
nova_cell_novncproxy_group: cell0001-vnc
nova_cell_conductor_group: cell0001-control
nova_cell_compute_group: cell0001-compute
```

#### **Passwords**

Kolla Ansible auto-generates passwords to a file, passwords.yml. Kayobe handles the orchestration of this, as well as encryption of the file using an Ansible Vault password specified in the KAYOBE\_VAULT\_PASSWORD environment variable, if present. The file is generated to \$KAYOBE\_CONFIG\_PATH/kolla/passwords.yml, and should be stored along with other Kayobe configuration files. This file should not be manually modified.

## **Configuring Custom Passwords**

The following variables are used to configure custom passwords:

- kolla\_ansible\_default\_custom\_passwords: Dictionary containing default custom passwords, required by Kolla Ansible. Contains SSH keys authorized by kolla user on Kolla hosts, SSH keys authorized in hosts deployed by Bifrost, Docker Registry password and compute libVirt custom passwords.
- kolla\_ansible\_extra\_custom\_passwords: Dictionary containing extra custom passwords to add or override in the Kolla passwords file. Default is an empty dictionary.
- kolla\_ansible\_custom\_passwords: Dictionary containing custom passwords to add or override in the Kolla passwords file. Default is the combination of the kolla\_ansible\_default\_custom\_passwords and kolla\_ansible\_extra\_custom\_passwords.

In this example we add our own my\_custom\_password and override keystone\_admin\_password:

Listing 131: \$KAYOBE\_CONFIG\_PATH/kolla.yml

```
# Dictionary containing extra custom passwords to add or override in the # Kolla passwords file.

kolla_ansible_extra_custom_passwords:

my_custom_password: 'correcthorsebatterystaple'
keystone_admin_password: 'superduperstrongpassword'
```

## **Control Plane Services**

Kolla Ansible provides a flexible mechanism for configuring the services that it deploys. Kayobe adds some commonly required configuration options to the defaults provided by Kolla Ansible, but also allows for the free-form configuration supported by Kolla Ansible. The Kolla Ansible documentation should be used as a reference.

# **Enabling Services**

Services deployed by Kolla Ansible are enabled via flags.

#### kolla\_enable\_<service or feature>

There are various flags that can be used to enable features. These map to variables named enable\_<service or feature> in Kolla Ansible. The default set of enabled services and features is the same as in Kolla ansible, except that Ironic is enabled by default in Kayobe.

## Example: enabling a service

A common task is enabling a new OpenStack service. This may be done via the kolla\_enable\_\* flags, for example:

Listing 132: \$KAYOBE\_CONFIG\_PATH/kolla.yml

```
kolla_enable_swift: true
```

Note that in some cases additional configuration may be required to successfully deploy a service - check the Kolla Ansible configuration reference.

### **Service Configuration**

Kolla-ansibles flexible configuration is described in the Kolla Ansible service configuration documentation. We wont duplicate that here, but essentially it involves creating files under a directory which for users of kayobe will be \$KOLLA\_CONFIG\_PATH/config. In kayobe, files in this directory are autogenerated and managed by kayobe. Instead, users should create files under \$KAYOBE\_CONFIG\_PATH/kolla/config with the same directory structure. These files will be templated using Jinja2, merged with kayobes own configuration, and written out to \$KOLLA\_CONFIG\_PATH/config.

The following files, if present, will be templated and provided to Kolla Ansible. All paths are relative to \$KAYOBE\_CONFIG\_PATH/kolla/config. Note that typically Kolla Ansible does not use the same wildcard patterns, and has a more restricted set of files that it will process. In some cases, it may be necessary to inspect the Kolla Ansible configuration tasks to determine which files are supported.

File Purpose aodh.conf Aodh configuration. aodh/\* Extended Aodh configuration. backup.my.cnf Mariabackup configuration. barbican.conf Barbican configuration. barbican/\* Extended Barbican configuration. blazar.conf Blazar configuration. blazar/\* Extended Blazar configuration. ceilometer.conf Ceilometer configuration. Extended Ceilometer configuration. ceilometer/\* cinder.conf Cinder configuration. cinder/\* Extended Cinder configuration. cloudkitty.conf CloudKitty configuration. Extended CloudKitty configuration. cloudkitty/\* Designate configuration. designate.conf designate/\* Extended Designate configuration. fluentd/filter Fluentd filter configuration. Fluentd input configuration. fluentd/input fluentd/output Fluentd output configuration. galera.cnf MariaDB configuration. glance.conf Glance configuration.

Table 1: Kolla-ansible configuration files

Table 1 – continued from previous page

File	Purpose
glance/*	Extended Glance configuration.
global.conf	Global configuration for all OpenStack services.
gnocchi.conf	Gnocchi configuration.
gnocchi/*	Extended Gnocchi configuration.
grafana.ini	Grafana configuration.
grafana/*	Extended Grafana configuration.
haproxy/*	Main HAProxy configuration.
haproxy-config/*	Modular HAProxy configuration.
heat.conf	Heat configuration.
heat/*	Extended heat configuration.
horizon/*	Extended horizon configuration.
influx*	InfluxDB configuration.
<pre>ironic-inspector.conf</pre>	Ironic inspector configuration.
ironic-inspector/*	Extended Ironic inspector configuration
ironic.conf	Ironic configuration.
ironic/*	Extended ironic configuration.
keepalived/*	Extended keepalived configuration.
keystone.conf	Keystone configuration.
keystone/*	Extended keystone configuration.
magnum.conf	Magnum configuration.
magnum/*	Extended magnum configuration.
manila.conf	Manila configuration.
manila/*	Extended manila configuration.
mariadb/*	Extended MariaDB configuration.
masakari.conf	Masakari configuration.
masakari/*	Extended masakari configuration.
multipath.conf	Multipathd configuration.
neutron.conf	Neutron configuration.
neutron/ml2_conf.ini	Neutron ML2 configuration.
neutron/*	Extended neutron configuration.
nova.conf	Nova configuration.
nova/*	Extended nova configuration.
octavia.conf	Octavia configuration.
octavia/*	Extended Octavia configuration.
opensearch/*	OpenSearch configuration.
placement.conf	Placement configuration.
placement/*	Extended Placement configuration.
prometheus/*	Prometheus configuration.
swift/*	Extended swift configuration.
telegraf/*	Extended Telegraf configuration.

## **Configuring an OpenStack Component**

To provide custom configuration to be applied to all glance services, create \$KAYOBE\_CONFIG\_PATH/kolla/config/glance.conf. For example:

Listing 133: \$KAYOBE\_CONFIG\_PATH/kolla/config/glance.
conf

```
[DEFAULT]
api_limit_max = 500
```

# Configuring an OpenStack Service

To provide custom configuration for the glance API service, create \$KAYOBE\_CONFIG\_PATH/kolla/config/glance/glance-api.conf. For example:

Listing 134: \$KAYOBE\_CONFIG\_PATH/kolla/config/glance/
glance-api.conf

```
[DEFAULT]
api_limit_max = 500
```

#### **Bifrost**

This section covers configuration of the Bifrost service that runs on the seed host. Bifrost configuration is typically applied in \${KAYOBE\_CONFIG\_PATH}/bifrost.yml. Consult the Bifrost documentation for further details of Bifrost usage and configuration.

#### **Bifrost installation**

#### Note

This section may be skipped if using an upstream Bifrost container image.

The following options are used if building the Bifrost container image locally.

#### kolla\_bifrost\_source\_url

URL of Bifrost source code repository. Default is https://opendev.org/openstack/bifrost.

#### kolla\_bifrost\_source\_version

Version (branch, tag, etc.) of Bifrost source code repository. Default is {{ openstack\_branch }}, which is the same as the Kayobe upstream branch name.

For example, to install Bifrost from a custom git repository:

```
Listing 135: bifrost.yml
```

```
kolla_bifrost_source_url: https://git.example.com/bifrost
kolla_bifrost_source_version: downstream
```

### **Bifrost interface configuration**

Following option allows to configure ipv4 interface MAC for the provisioned server in cases where the default (PXE interface MAC) is not a suitable solution for admin network (e.g. separate interfaces for provisioning and admin):

Listing 136: bifrost.yml

```
kolla_bifrost_use_introspection_mac: true
```

It will cause the overloud provision command to query Bifrosts Introspection data for MAC address of the interface that is bound to admin network. Limitation of that option is that Kayobe will use the first physical NIC if the interface is bond or bridge.

Alternatively you can set following in host\_vars of a specific host:

Listing 137: host\_vars

```
kolla_bifrost_ipv4_interface_mac: "<mac_address_goes_here>"
```

## Overcloud root disk image configuration

#### Note

This configuration only applies when overcloud\_dib\_build\_host\_images (set in \${KAYOBE\_CONFIG\_PATH}/overcloud-dib.yml) is changed to false.

Bifrost uses Diskimage builder (DIB) to build a root disk image that is deployed to overcloud hosts when they are provisioned. The following options configure how this image is built. Consult the Diskimage-builder documentation for further information on building disk images.

The default configuration builds a whole disk (partitioned) image using the selected *OS distribution* with serial console enabled, and SELinux disabled if CentOS Stream is used. Rocky Linux 9 users should use the default method of building images with *Diskimage builder directly*.

#### kolla\_bifrost\_dib\_os\_element

DIB base OS element. Default is {{ os\_distribution }}.

### kolla\_bifrost\_dib\_os\_release

DIB image OS release. Default is {{ os\_release }}.

#### kolla\_bifrost\_dib\_elements\_default

Added in the Train release. Use kolla\_bifrost\_dib\_elements in earlier releases.

List of default DIB elements. Default is ["enable-serial-console", "vm"]. The vm element is poorly named, and causes DIB to build a whole disk image rather than a single partition.

#### kolla\_bifrost\_dib\_elements\_extra

Added in the Train release. Use kolla\_bifrost\_dib\_elements in earlier releases.

List of additional DIB elements. Default is none.

#### kolla\_bifrost\_dib\_elements

List of DIB elements. Default is a combination of kolla\_bifrost\_dib\_elements\_default and kolla\_bifrost\_dib\_elements\_extra.

### kolla\_bifrost\_dib\_init\_element

DIB init element. Default is cloud-init-datasources.

## kolla\_bifrost\_dib\_env\_vars\_default

Added in the Train release. Use kolla\_bifrost\_dib\_env\_vars in earlier releases.

DIB default environment variables. Default is {DIB\_BOOTLOADER\_DEFAULT\_CMDLINE: "nofb nomodeset gfxpayload=text net.ifnames=1", "DIB\_CLOUD\_INIT\_DATASOURCES": "ConfigDrive"}.

#### kolla\_bifrost\_dib\_env\_vars\_extra

Added in the Train release. Use kolla\_bifrost\_dib\_env\_vars in earlier releases.

DIB additional environment variables. Default is none.

#### kolla\_bifrost\_dib\_env\_vars

DIB environment variables. Default is combination of kolla\_bifrost\_dib\_env\_vars\_default and kolla\_bifrost\_dib\_env\_vars\_extra.

### kolla\_bifrost\_dib\_packages

List of DIB packages to install. Default is to install no extra packages.

The disk image is built during the deployment of seed services. It is worth noting that currently, the image will not be rebuilt if it already exists. To force rebuilding the image, it is necessary to remove the file. On the seed:

docker exec bifrost\_deploy rm /httpboot/deployment\_image.gcow2

Then on the control host:

(kayobe) \$ kayobe seed service deploy

### **Example: Adding an element**

In the following, we extend the list of DIB elements to add the growpart element:

# Listing 138: bifrost.yml

```
kolla_bifrost_dib_elements_extra:
- "growpart"
```

## **Example: Building an XFS root filesystem image**

By default, DIB will format the image as ext4. In some cases it might be useful to use XFS, for example when using the overlay Docker storage driver which can reach the maximum number of hardlinks allowed by ext4.

In DIB, we achieve this by setting the FS\_TYPE environment variable to xfs.

```
Listing 139: bifrost.yml
```

```
kolla_bifrost_dib_env_vars_extra:
FS_TYPE: "xfs"
```

## **Example: Configuring a development user account**

## Warning

A development user account should not be used in production.

When debugging a failed deployment, it can sometimes be necessary to allow access to the image via a preconfigured user account with a known password. This can be achieved via the devuser element.

This example shows how to add the devuser element, and configure a username and password for an account that has passwordless sudo:

#### Listing 140: bifrost.yml

```
kolla_bifrost_dib_elements_extra:
- "devuser"

kolla_bifrost_dib_env_vars_extra:
DIB_DEV_USER_USERNAME: "devuser"
DIB_DEV_USER_PASSWORD: "correct horse battery staple"
DIB_DEV_USER_PWDLESS_SUDO: "yes"
```

Alternatively, the dynamic-login element can be used to authorize SSH keys by appending them to the kernel arguments.

### Example: Installing a package

It can be necessary to install additional packages in the root disk image. Rather than needing to write a custom DIB element, we can use the kolla\_bifrost\_dib\_packages variable. For example, to install the biosdevname package:

Listing 141: bifrost.yml

```
kolla_bifrost_dib_packages:
- "biosdevname"
```

## Disk image deployment configuration

The name of the root disk image to deploy can be configured via the kolla\_bifrost\_deploy\_image\_filename option, which defaults to deployment\_image.qcow2. It can be defined globally in \${KAYOBE\_CONFIG\_PATH}/bifrost.yml, or defined per-group or per-host in the Kayobe inventory. This can be used to provision different images across the overcloud.

It can be necessary to deploy overcloud hosts with custom settings which can be configured during provision by the cloud-init user-data configured via the kolla\_bifrost\_deploy\_image\_user\_data\_content option. The defaults is an empty string.

Listing 142: bifrost.yml

```
kolla_bifrost_deploy_image_user_data_content:
    users:
    name: myuser
    sudo: ALL=(ALL) NOPASSWD:ALL
    shell: /bin/bash
    passwd: <HASH_OF_MY_PASSWORD>
    lock_passwd: false

timezone: "Europe/Paris"
```

While only a single disk image can be built with Bifrost, starting from the Yoga 12.0.0 release, Kayobe supports building multiple disk images directly through Diskimage builder. Consult the *overcloud host disk image build documentation* for more details.

### Ironic configuration

The following options configure the Ironic service in the bifrost-deploy container.

### kolla\_bifrost\_enabled\_hardware\_types

List of hardware types to enable for Bifrosts Ironic. Default is ["ipmi"].

### kolla\_bifrost\_extra\_kernel\_options

List of extra kernel parameters for Bifrosts Ironic PXE configuration. Default is none.

## **Ironic Inspector configuration**

The following options configure the Ironic Inspector service in the bifrost-deploy container.

### kolla\_bifrost\_inspector\_processing\_hooks

List of of inspector processing plugins. Default is {{ inspector\_processing\_hooks }}, defined in \${KAYOBE\_CONFIG\_PATH}/inspector.yml.

### kolla\_bifrost\_inspector\_port\_addition

Which MAC addresses to add as ports during introspection. One of all, active or pxe. Default is {{ inspector\_add\_ports }}, defined in \${KAYOBE\_CONFIG\_PATH}/inspector.yml.

### kolla\_bifrost\_inspector\_extra\_kernel\_options

List of extra kernel parameters for the inspector default PXE configuration. Default is {{ inspector\_extra\_kernel\_options }}, defined in \${KAYOBE\_CONFIG\_PATH}/inspector. yml. When customising this variable, the default extra kernel parameters should be kept to retain full node inspection capabilities.

#### kolla\_bifrost\_inspector\_rules

List of introspection rules for Bifrosts Ironic Inspector service. Default is {{ inspector\_rules }}, defined in \${KAYOBE\_CONFIG\_PATH}/inspector.yml.

### kolla\_bifrost\_inspector\_ipmi\_username

Ironic inspector IPMI username to set via an introspection rule. Default is {{ ipmi\_username }}, defined in \${KAYOBE\_CONFIG\_PATH}/bmc.yml.

#### kolla\_bifrost\_inspector\_ipmi\_password

Ironic inspector IPMI password to set via an introspection rule. Default is {{ ipmi\_password }}, defined in \${KAYOBE\_CONFIG\_PATH}/bmc.yml.

### kolla\_bifrost\_inspector\_lldp\_switch\_port\_interface

Ironic inspector network interface name on which to check for an LLDP switch port description to use as the nodes name. Default is {{ inspector\_lldp\_switch\_port\_interface\_default }}, defined in \${KAYOBE\_CONFIG\_PATH}/inspector.yml.

#### kolla\_bifrost\_inspector\_deploy\_kernel

Ironic inspector deployment kernel location. Default is http://{{ provision\_oc\_net\_name | net\_ip }}:8080/ipa.kernel.

#### kolla\_bifrost\_inspector\_deploy\_ramdisk

Ironic inspector deployment ramdisk location. Default is http://{{ provision\_oc\_net\_name | net\_ip }}:8080/ipa.initramfs.

### kolla\_bifrost\_inspection\_timeout

Timeout of hardware inspection on overcloud nodes, in seconds. Default is {{

inspector\_inspection\_timeout }}, defined in \${KAYOBE\_CONFIG\_PATH}/inspector.
yml.

### kolla\_bifrost\_inspector\_redfish\_username

Ironic inspector Redfish username to set via an introspection rule. Defined in \${KAYOBE\_CONFIG\_PATH}/bifrost.yml. Default is {{ inspector\_redfish\_username }}.

## kolla\_bifrost\_inspector\_redfish\_password

Ironic inspector Redfish username to set via an introspection rule. Defined in \${KAYOBE\_CONFIG\_PATH}/bifrost.yml. Default is {{ inspector\_redfish\_username }}.

## Ironic Python Agent (IPA) configuration

#### Note

If building IPA images locally (ipa\_build\_images is true) this section can be skipped.

The following options configure the source of Ironic Python Agent images used by Bifrost for inspection and deployment. Consult the Ironic Python Agent documentation for full details.

### kolla\_bifrost\_ipa\_kernel\_upstream\_url

URL of Ironic Python Agent (IPA) kernel image. Default is {{ inspector\_ipa\_kernel\_upstream\_url }}, defined in \${KAYOBE\_CONFIG\_PATH}/inspector.yml.

## kolla\_bifrost\_ipa\_kernel\_checksum\_url

URL of checksum of Ironic Python Agent (IPA) kernel image. Default is {{ inspector\_ipa\_kernel\_checksum\_url }}, defined in \${KAYOBE\_CONFIG\_PATH}/inspector.yml.

## kolla\_bifrost\_ipa\_kernel\_checksum\_algorithm

Algorithm of checksum of Ironic Python Agent (IPA) kernel image. Default is {{ inspector\_ipa\_kernel\_checksum\_algorithm }}, defined in \${KAYOBE\_CONFIG\_PATH}/inspector.yml.

#### kolla\_bifrost\_ipa\_ramdisk\_upstream\_url

URL of Ironic Python Agent (IPA) ramdisk image. Default is {{ inspector\_ipa\_ramdisk\_upstream\_url }}, defined in \${KAYOBE\_CONFIG\_PATH}/inspector.yml.

## kolla\_bifrost\_ipa\_ramdisk\_checksum\_url

URL of checksum of Ironic Python Agent (IPA) ramdisk image. Default is {{ inspector\_ipa\_ramdisk\_checksum\_url }}, defined in \${KAYOBE\_CONFIG\_PATH}/inspector.yml.

## kolla\_bifrost\_ipa\_ramdisk\_checksum\_algorithm

Algorithm of checksum of Ironic Python Agent (IPA) ramdisk image. Default is {{ inspector\_ipa\_ramdisk\_checksum\_algorithm }}, defined in \${KAYOBE\_CONFIG\_PATH}/ inspector.yml.

### **Inventory configuration**

#### Note

This feature is currently not well tested. It is advisable to use autodiscovery of overcloud servers instead.

The following option is used to configure a static inventory of servers for Bifrost.

kolla\_bifrost\_servers

Server inventory for Bifrost in the JSON file format.

### **Custom Configuration**

Further configuration of arbitrary Ansible variables for Bifrost can be provided via the following files:

- \${KAYOBE\_CONFIG\_PATH}/kolla/config/bifrost/bifrost.yml
- \${KAYOBE\_CONFIG\_PATH}/kolla/config/bifrost/dib.yml

These are both passed as extra variables files to ansible-playbook, but the naming scheme provides a separation of DIB image related variables from other variables. It may be necessary to inspect the Bifrost source code for the full set of variables that may be configured.

For example, to configure debug logging for Ironic Inspector:

Listing 143: kolla/config/bifrost/bifrost.yml

inspector\_debug: true

# Overcloud host disk image build

This section covers configuration for building overcloud host disk images with Diskimage builder (DIB), which is available from the Yoga 12.0.0 release. This configuration is applied in \${KAYOBE\_CONFIG\_PATH}/overcloud-dib.yml.

### **Enabling host disk image build**

From the Yoga release, disk images for overcloud hosts can be built directly using Diskimage builder rather than through Bifrost. This is enabled with the following option:

## overcloud\_dib\_build\_host\_images

Whether to build host disk images with DIB directly instead of through Bifrost. Setting it to true disables Bifrost image build and allows images to be built with the kayobe overcloud host image build command. Default value is true since the Zed release.

With this option enabled, Bifrost will be configured to stop building a root disk image. This will become the default behaviour in a future release.

## Overcloud root disk image configuration

Kayobe uses Diskimage builder (DIB) to build root disk images that are deployed to overcloud hosts when they are provisioned. The following options configure how these images are built. Consult the Diskimage-builder documentation for further information on building disk images.

The default configuration builds a whole disk (partitioned) image using the selected *OS distribution* (Rocky Linux 9 by default) with serial console enabled, and SELinux disabled if CentOS Stream or Rocky Linux is used. Cloud-init is used to process the configuration drive built by Bifrost during provisioning.

## overcloud\_dib\_host\_packages\_extra

List of additional host packages to install. Default is an empty list.

#### overcloud\_dib\_host\_images

List of overcloud host disk images to build. Each element is a dict defining an image in a format accepted by the stackhpc.openstack.os\_images role. Default is to build an image named deployment\_image configured with the overcloud\_dib\_\* variables defined below: {"name": "deployment\_image", "elements": "{{ overcloud\_dib\_elements }}", "env": "{{ overcloud\_dib\_env\_vars }}", "packages": "{{ overcloud\_dib\_packages }}"}.

#### overcloud\_dib\_os\_element

```
DIB base OS element. Default is {{ 'rocky-container' if os_distribution == 'rocky' else os_distribution }}.
```

## overcloud\_dib\_os\_release

DIB image OS release. Default is {{ os\_release }}.

#### overcloud\_dib\_elements\_default

List of default DIB elements. Default is ["{{ overcloud\_dib\_os\_element }}", "cloud-init-datasources", "enable-serial-console", "vm"]. The vm element is poorly named, and causes DIB to build a whole disk image rather than a single partition.

#### overcloud\_dib\_elements\_extra

List of additional DIB elements. Default is none.

### overcloud\_dib\_elements

List of DIB elements. Default is a combination of overcloud\_dib\_elements\_default and overcloud\_dib\_elements\_extra.

#### overcloud\_dib\_env\_vars\_default

```
DIB default environment variables. Default is {"DIB_BOOTLOADER_DEFAULT_CMDLINE": "nofb nomodeset gfxpayload=text net.ifnames=1", "DIB_CLOUD_INIT_DATASOURCES": "ConfigDrive", "DIB_CONTAINERFILE_RUNTIME": "docker", "DIB_CONTAINERFILE_NETWORK_DRIVER": "host", DIB_RELEASE": "{{ overcloud_dib_os_release }}"}.
```

#### overcloud\_dib\_env\_vars\_extra

DIB additional environment variables. Default is none.

#### overcloud\_dib\_env\_vars

DIB environment variables. Default is combination of overcloud\_dib\_env\_vars\_default and overcloud\_dib\_env\_vars\_extra.

#### overcloud\_dib\_packages

List of DIB packages to install. Default is to install no extra packages.

## overcloud\_dib\_git\_elements\_default

List of default git repositories containing Diskimage Builder (DIB) elements. See stackhpc.openstack.os\_images role for usage. Default is empty.

# overcloud\_dib\_git\_elements\_extra

List of additional git repositories containing Diskimage Builder (DIB) elements. See stackhpc.openstack.os\_imagesimages role for usage. Default is empty.

#### overcloud\_dib\_git\_elements

List of git repositories containing Diskimage Builder (DIB) elements. See stackhpc.openstack.os\_images role for usage. Default is a combination of overcloud\_dib\_git\_elements\_default and overcloud\_dib\_git\_elements\_extra.

### overcloud\_dib\_upper\_constraints\_file

Upper constraints file for installing packages in the virtual environment used for building overcloud host disk images. Default is {{ pip\_upper\_constraints\_file }}.

### overcloud\_dib\_dib\_upper\_constraints\_file

Upper constraints file for installation of DIB to build overcloud host disk images. Default is empty string.

Disk images are built with the following command:

```
(kayobe) $ kayobe overcloud host image build
```

It is worth noting that images will not be rebuilt if they already exist. To force rebuilding images, it is necessary to use the --force-rebuild argument.

```
(kayobe) $ kayobe overcloud host image build --force-rebuild
```

## **Example: Adding an element**

In the following, we extend the list of DIB elements to add the growpart element:

Listing 144: dib.yml

```
overcloud_dib_elements_extra:
    "growpart"
```

## **Example: Building an XFS root filesystem image**

By default, DIB will format the image as ext4. In some cases it might be useful to use XFS, for example when using the overlay Docker storage driver which can reach the maximum number of hardlinks allowed by ext4.

In DIB, we achieve this by setting the FS\_TYPE environment variable to xfs.

Listing 145: dib.yml

```
overcloud_dib_env_vars_extra:
   FS_TYPE: "xfs"
```

### **Example: Configuring a development user account**

## Warning

A development user account should not be used in production.

When debugging a failed deployment, it can sometimes be necessary to allow access to the image via a preconfigured user account with a known password. This can be achieved via the devuser element.

This example shows how to add the devuser element, and configure a username and password for an account that has passwordless sudo:

Listing 146: dib.yml

```
overcloud_dib_elements_extra:
    "devuser"

overcloud_dib_env_vars_extra:
    DIB_DEV_USER_USERNAME: "devuser"
    DIB_DEV_USER_PASSWORD: "correct horse battery staple"
    DIB_DEV_USER_PWDLESS_SUDO: "yes"
```

Alternatively, the dynamic-login element can be used to authorize SSH keys by appending them to the kernel arguments.

## **Example: Configuring custom DIB elements**

Sometimes it is useful to use custom DIB elements that are not shipped with DIB itself. This can be done by sharing them in a git repository.

### Listing 147: overcloud-dib.yml

```
overcloud_dib_elements_extra:
    "my-element"

overcloud_dib_git_elements:
    repo: "https://git.example.com/custom-dib-elements"
    local: "{{ source_checkout_path }}/custom-dib-elements"
    version: "master"
    elements_path: "elements"
```

In this example the master branch of https://git.example.com/custom-dib-elements would have a top level elements directory, containing a my-element directory for the element.

### Example: Installing a package

It can be necessary to install additional packages in the root disk image. Rather than needing to write a custom DIB element, we can use the overcloud\_dib\_packages variable. For example, to install the biosdevname package:

Listing 148: dib.yml

```
overcloud_dib_packages:
    - "biosdevname"
```

## **Example: Building multiple images**

It can be necessary to build multiple images to support the various types of hardware present in a deployment or the different functions performed by overcloud hosts. This can be configured with the overcloud\_dib\_host\_images variable, using a format accepted by the stackhpc.openstack.os\_images role. Note that image names should not include the file extension. For example, to build a second image with a development user account and the biosdevname package:

Listing 149: dib.yml

```
overcloud_dib_host_images:
    name: "deployment_image"
    elements: "{{      overcloud_dib_elements }}"
    env: "{{       overcloud_dib_env_vars }}"
    packages: "{{            overcloud_dib_packages }}"
    - name: "debug_deployment_image"
    elements: "{{            overcloud_dib_elements + ['devuser'] }}"
    env: "{{            overcloud_dib_env_vars | combine(devuser_env_vars) }}"
    packages: "{{            overcloud_dib_packages + ['biosdevname'] }}"

devuser_env_vars:
    DIB_DEV_USER_USERNAME: "devuser"
    DIB_DEV_USER_PASSWORD: "correct horse battery staple"
    DIB_DEV_USER_PWDLESS_SUDO: "yes"
```

Running the kayobe overcloud host image build command with this configuration will create two images: deployment\_image.qcow2 and debug\_deployment\_image.qcow2.

# Disk image deployment configuration

See *disk image deployment configuration in Bifrost* for how to configure the root disk image to be used to provision each host.

### **Ironic Python Agent (IPA)**

This section covers configuration of Ironic Python Agent (IPA) which is used by Ironic and Ironic Inspector to deploy and inspect bare metal nodes. This is used by the Bifrost services that run on the seed host, and also by Ironic and Ironic Inspector services running in the overcloud for bare metal compute, if enabled (kolla\_enable\_ironic is true). IPA configuration is typically applied in \${KAYOBE\_CONFIG\_PATH}/ipa.yml. Consult the IPA documentation for full details of IPA usage and configuration.

# Ironic Python Agent (IPA) image build configuration

#### Note

This section may be skipped if not building IPA images locally (ipa\_build\_images is false).

The following options cover building of IPA images via Diskimage-builder (DIB). Consult the Diskimage-builder documentation for full details.

The default configuration builds a CentOS Stream 9 ramdisk image which includes the upstream IPA source code, and has a serial console enabled.

The images are built for Bifrost via kayobe seed deployment image build, and for Ironic in the overcloud (if enabled) via kayobe overcloud deployment image build.

#### ipa\_build\_images

Whether to build IPA images from source. Default is False.

#### ipa\_build\_source\_url

URL of IPA source repository. Default is https://opendev.org/openstack/ironic-python-agent

#### ipa\_build\_source\_version

Version of IPA source repository. Default is {{ openstack\_branch }}.

#### ipa\_builder\_source\_url

URL of IPA builder source repository. Default is https://opendev.org/openstack/ironic-python-agent-builder

### ipa\_builder\_source\_version

Version of IPA builder source repository. Default is master.

### ipa\_build\_dib\_host\_packages\_extra

List of additional build host packages to install. Default is an empty list.

#### ipa\_build\_dib\_elements\_default

List of default Diskimage Builder (DIB) elements to use when building IPA images. Default is ["centos", "enable-serial-console", "ironic-python-agent-ramdisk"] when os\_distribution is "rocky", and ["ubuntu", "enable-serial-console", "ironic-python-agent-ramdisk"] otherwise.

#### ipa\_build\_dib\_elements\_extra

List of additional Diskimage Builder (DIB) elements to use when building IPA images. Default is empty.

### ipa\_build\_dib\_elements

List of Diskimage Builder (DIB) elements to use when building IPA images. Default is combination of ipa\_build\_dib\_elements\_default and ipa\_build\_dib\_elements\_extra.

#### ipa\_build\_dib\_env\_default

```
Dictionary of default environment variables to provide to Diskimage Builder (DIB) during IPA image build. Default is {"DIB_RELEASE": "9-stream", "DIB_REPOLOCATION_ironic_python_agent": "{{ ipa_build_source_url }}", "DIB_REPOREF_ironic_python_agent": "{{ ipa_build_source_version }}", "DIB_REPOREF_requirements": "{{ ipa_build_source_version }}"} if os_distribution is "rocky" else {"DIB_RELEASE": "{{ os_release }}", "DIB_REPOLOCATION_ironic_python_agent": "{{ ipa_build_source_url }}", "DIB_REPOREF_ironic_python_agent": "{{ ipa_build_source_version }}", "DIB_REPOREF_requirements": "{{ ipa_build_source_version }}"}.
```

### ipa\_build\_dib\_env\_extra

Dictionary of additional environment variables to provide to Diskimage Builder (DIB) during IPA image build. Default is empty.

#### ipa\_build\_dib\_env

Dictionary of environment variables to provide to Diskimage Builder (DIB) during IPA image build. Default is a combination of ipa\_build\_dib\_env\_default and ipa\_build\_dib\_env\_extra.

#### ipa\_build\_dib\_git\_elements\_default

List of default git repositories containing Diskimage Builder (DIB) elements. See stackhpc.openstack.os\_images role for usage. Default is one item for IPA builder.

#### ipa\_build\_dib\_git\_elements\_extra

List of additional git repositories containing Diskimage Builder (DIB) elements. See stackhpc.openstack.os\_images role for usage. Default is none.

#### ipa\_build\_dib\_git\_elements

List of git repositories containing Diskimage Builder (DIB) elements. See stackhpc.openstack.os\_images role for usage. Default is combination of ipa\_build\_dib\_git\_elements\_default and ipa\_build\_dib\_git\_elements\_extra.

#### ipa\_build\_dib\_packages

List of DIB packages to install. Default is none.

## ipa\_build\_upper\_constraints\_file

Upper constraints file for installing packages in the virtual environment used for building IPA images. Default is {{ pip\_upper\_constraints\_file }}.

## **Example: Building IPA images locally**

To build IPA images locally:

Listing 150: ipa.yml

```
ipa_build_images: true
```

# **Example: Installing IPA from a custom git repository**

To install IPA from a custom git repository:

```
Listing 151: ipa.yml
```

```
ipa_source_url: https://git.example.com/ironic-python-agent
ipa_source_version: downstream
```

### **Example: Adding an element**

In the following example, we extend the list of DIB elements to add the mellanox element, which can be useful for inspecting hardware with Mellanox InfiniBand NICs.

```
Listing 152: ipa.yml
```

```
ipa_build_dib_elements_extra:
    "mellanox"
```

## **Example: Configuring a development user account**

#### Warning

A development user account should not be used in production.

When debugging a failed deployment, it can sometimes be necessary to allow access to the image via a preconfigured user account with a known password. This can be achieved via the devuser element.

This example shows how to add the devuser element, and configure a username and password for an account that has passwordless sudo:

Listing 153: ipa.yml

```
ipa_build_dib_elements_extra:
    "devuser"

ipa_build_dib_env_extra:
    DIB_DEV_USER_USERNAME: "devuser"
```

```
DIB_DEV_USER_PASSWORD: "correct horse battery staple"
DIB_DEV_USER_PWDLESS_SUDO: "yes"
```

Alternatively, the dynamic-login element can be used to authorize SSH keys by appending them to the kernel arguments.

Further information on troubleshooting IPA can be found here.

# **Example: Configuring custom DIB elements**

Sometimes it is useful to use custom DIB elements that are not shipped with DIB itself. This can be done by sharing them in a git repository.

Listing 154: ipa.yml

```
ipa_build_dib_elements_extra:
    "my-element"

ipa_build_dib_git_elements:
    repo: "https://git.example.com/custom-dib-elements"
    local: "{{ source_checkout_path }}/custom-dib-elements"
    version: "master"
    elements_path: "elements"
```

In this example the master branch of https://git.example.com/custom-dib-elements would have a top level elements directory, containing a my-element directory for the element.

## Example: Installing a package

It can be necessary to install additional packages in the IPA image. Rather than needing to write a custom DIB element, we can use the ipa\_build\_dib\_packages variable. For example, to install the biosdevname package:

Listing 155: ipa.yml

```
ipa_build_dib_packages:
    - "biosdevname"
```

# Ironic Python Agent (IPA) images configuration

### Note

If building IPA images locally (ipa\_build\_images is true) this section can be skipped.

The following options configure the source of Ironic Python Agent images for inspection and deployment. Consult the Ironic Python Agent documentation for full details.

### ipa\_images\_upstream\_url\_suffix

Suffix of upstream Ironic deployment image files. Default is based on {{ openstack\_branch }}.

## ipa\_images\_kernel\_name

Name of Ironic deployment kernel image to register in Glance. Default is ipa.kernel.

## ipa\_kernel\_upstream\_url

URL of Ironic deployment kernel image to download. Default is https://tarballs.openstack.org/ironic-python-agent/dib/files/ipa-centos9{{ipa\_images\_upstream\_url\_suffix }}.kernel.

### ipa\_kernel\_checksum\_url

URL of checksum of Ironic deployment kernel image. Default is {{
ipa\_kernel\_upstream\_url }}.{{ ipa\_kernel\_checksum\_algorithm }}.

# ipa\_kernel\_checksum\_algorithm

Algorithm of checksum of Ironic deployment kernel image. Default is sha256.

### ipa\_images\_ramdisk\_name

Name of Ironic deployment ramdisk image to register in Glance. Default is ipa.initramfs.

### ipa\_ramdisk\_upstream\_url

URL of Ironic deployment ramdisk image to download. Default is https://tarballs.openstack.org/ironic-python-agent/dib/files/ipa-centos9{{ipa\_images\_upstream\_url\_suffix }}.initramfs.

## ipa\_ramdisk\_checksum\_url

URL of checksum of Ironic deployment ramdisk image. Default is {{
ipa\_ramdisk\_upstream\_url }}.{{ ipa\_ramdisk\_checksum\_algorithm }}.

### ipa\_ramdisk\_checksum\_algorithm

Algorithm of checksum of Ironic deployment ramdisk image. Default is sha256.

#### Ironic Python Agent (IPA) deployment configuration

The following options configure how IPA operates during deployment and inspection.

#### ipa\_collect\_lldp

Whether to enable collection of LLDP TLVs. Default is True.

#### ipa\_collectors\_default

## Note

extra-hardware is not currently included as it requires a ramdisk with the hardware python module installed.

List of default inspection collectors to run. Default is ["default", "logs", "pci-devices"].

## ipa\_collectors\_extra

List of additional inspection collectors to run. Default is none.

# ipa\_collectors

List of inspection collectors to run. Default is a combination of ipa\_collectors\_default and ipa\_collectors\_extra.

# ipa\_benchmarks\_default

List of default inspection benchmarks to run. Default is ["cpu", "disk", "ram"].

### ipa\_benchmarks\_extra

List of extra inspection benchmarks to run. Default is none.

#### ipa\_benchmarks

#### Note

The extra-hardware collector must be enabled in order to execute benchmarks during inspection.

List of inspection benchmarks to run. Default is a combination of ipa\_benchmarks\_default and ipa\_benchmarks\_extra.

## ipa\_kernel\_options\_default

List of default kernel parameters for Ironic python agent. Default includes ipa-collect-lldp, ipa-inspection-collectors and ipa-inspection-benchmarks, with arguments taken from ipa\_collect\_lldp, ipa\_collectors and ipa\_benchmarks.

### ipa\_kernel\_options\_extra

List of additional kernel parameters for Ironic python agent. Default is none.

# ipa\_kernel\_options

List of kernel parameters for Ironic python agent. Default is a combination of ipa\_kernel\_options\_default and ipa\_kernel\_options\_extra.

#### Example: Adding the extra-hardware collector

The extra-hardware collector may be used to collect additional information about hardware during inspection. It is also a requirement for running benchmarks. This collector depends on the Python hardware package, which is not installed in IPA images by default.

The following example enables the extra-hardware collector:

## Listing 156: ipa.yml

```
ipa_collectors_extra:
    "extra-hardware"
```

The ironic-python-agent-builder repository provides an extra-hardware element which may be used to install this package. It may be used as follows if building an IPA image locally:

#### Listing 157: ipa.yml

```
ipa_build_dib_elements_extra:
    - "extra-hardware"
```

### **Example: Passing additional kernel arguments to IPA**

The following example shows how to pass additional kernel arguments to IPA:

Listing 158: ipa.yml

```
ipa_kernel_options_extra:
    "foo=bar"
```

## **Docker registry**

This section covers configuration of the Docker registry that may be deployed, by default on the seed host. Docker registry configuration is typically applied in \${KAYOBE\_CONFIG\_PATH}/docker-registry.yml. Consult the Docker registry documentation for further details of registry usage and configuration.

The registry is deployed during the kayobe seed host configure command.

# **Configuring the registry**

### docker\_registry\_enabled

Whether a docker registry is enabled. Default is false. When set to true, the Docker registry is deployed on all hosts in the docker-registry group. By default this includes the seed host.

### docker\_registry\_env

Dict of environment variables to provide to the docker registry container. This allows to configure the registry by overriding specific configuration options, as described at https://docs.docker.com/registry/configuration/ For example, the registry can be configured as a pull through cache to Docker Hub by setting REGISTRY\_PROXY\_REMOTEURL to https://registry-1.docker.io. Note that it is not possible to push to a registry configured as a pull through cache. Default is {}.

#### docker\_registry\_network\_mode

The network mode used for the docker registry container. Default is host. When set to bridge, port mapping is configured to expose the registry through port docker\_registry\_port.

### docker\_registry\_port

The port on which the docker registry server should listen. Default is 4000. When docker\_registry\_network\_mode is set to host, configures the port used by the registry server inside the container. When docker\_registry\_network\_mode is set to bridge, configures the overlay network port.

#### docker\_registry\_datadir\_volume

Name or path to use as the volume for the docker registry. Default is docker\_registry.

#### TLS

It is recommended to enable TLS for the registry.

### docker\_registry\_enable\_tls

Whether to enable TLS for the registry. Default is false.

## docker\_registry\_cert\_path

Path to a TLS certificate to use when TLS is enabled. Default is none.

### docker\_registry\_key\_path

Path to a TLS key to use when TLS is enabled. Default is none.

For example, the certificate and key could be stored with the Kayobe configuration, under \${KAYOBE\_CONFIG\_PATH}/docker-registry/. These files may be encrypted via Ansible Vault.

### Listing 159: docker-registry.yml

```
docker_registry_enable_tls: true
docker_registry_cert_path: "{{ kayobe_config_path }}/docker-registry/cert.pem"
docker_registry_key_path: "{{ kayobe_config_path }}/docker-registry/key.pem"
```

#### **Basic authentication**

It is recommended to enable HTTP basic authentication for the registry. This needs to be done in conjunction with enabling TLS for the registry: using basic authentication over unencrypted HTTP is not supported.

### docker\_registry\_enable\_basic\_auth

Whether to enable basic authentication for the registry. Default is false.

## docker\_registry\_basic\_auth\_htpasswd\_path

Path to a htpasswd formatted password store for the registry. Default is none.

The password store uses a htpasswd format. The following example shows how to generate a password and add it to the kolla user in the password store. The password store may be stored with the Kayobe configuration, under \${KAYOBE\_CONFIG\_PATH}/docker-registry/. The file may be encrypted via Ansible Vault.

```
uuidgen | tr -d '\n' > registry-password
cat registry-password | docker run --rm -i --entrypoint htpasswd httpd:latest

→-niB kolla > $KAYOBE_CONFIG_PATH/docker-registry/htpasswd
```

Next we configure Kayobe to enable basic authentication for the registry, and specify the path to the password store.

### Listing 160: docker-registry.yml

## Using the registry

Enabling the registry does not automatically set the configuration for Docker engine to use it. This should be done via the *docker\_registry variable*.

#### **TLS**

If the registry is using a privately signed TLS certificate, it is necessary to *configure Docker engine with* the CA certificate.

If TLS is enabled, Docker engine should be configured to use HTTPS to communicate with it:

```
Listing 161: kolla/globals.yml
```

```
docker_registry_insecure: false
```

#### **Basic authentication**

If basic authentication is enabled, Kolla Ansible needs to be configured with the username and password.

### Listing 162: kolla.yml

```
kolla_docker_registry_username: <registry username>
kolla_docker_registry_password: <registry password>
```

#### Seed custom containers

This section covers configuration of the user-defined containers deployment functionality that runs on the seed host.

## Configuration

For example, to deploy a squid container image:

# Listing 163: seed.yml

Please notice the *optional* pre, post, pre\_destroy, and post\_destroy Ansible task files - those need to be created in kayobe-config path. The table below describes when they will run:

Table 2: Container hooks

Hook	Trigger point
pre	Before container deployment
post	After container deployment
pre_destroy	Before container is destroyed
post_destroy	After container is destroyed

Possible options for container deployment:

```
seed_containers:
 containerA
    capabilities:
    command:
    comparisons:
    detach:
    env:
    network_mode:
    image:
    init:
    ipc_mode:
    pid_mode:
    ports
    privileged:
    restart_policy:
    shm_size:
    sysctls:
    tag
    ulimits:
    user:
    volumes
```

For a detailed explanation of each option - please see Ansible docker\_container module page.

List of Kayobe applied defaults to required docker\_container variables:

```
# Action to perform: One of: "deploy", "destroy".

manage_containers_action: "deploy"

deploy_containers_defaults:
    comparisons:
    image: strict
    env: strict
    volumes: strict
    detach: True
    network_mode: "host"
    init: True
    privileged: False
    restart_policy: "unless-stopped"
```

### **Docker registry**

Seed containers can be pulled from a docker registry deployed on the seed, since the docker registry deployment step precedes the custom container deployment step.

It is also possible to deploy a custom containerised docker registry as a custom seed container. In this case, basic authentication login attempts can be disabled by setting

Listing 164: seed.yml

```
seed_deploy_containers_registry_attempt_login: false
```

Without this setting, the login will fail because the registry has not yet been deployed.

More information on deploying a docker registry can be found *here*.

#### Infrastructure VMs

Kayobe can deploy infrastructure VMs to the seed-hypervisor. These can be used to provide supplementary services that do not run well within a containerised environment or are dependencies of the control plane.

## Configuration

To deploy an infrastructure VM, add a new host to the infra-vms group in the inventory:

Listing 165: \$KAYOBE\_CONFIG\_PATH/inventory/infra-vms

```
[infra-vms]
an-example-vm
```

The configuration of the virtual machine should be done using host\_vars. These override the group\_vars defined for the infra-vms group. Most variables have sensible defaults defined, but there are a few variables which must be set.

## **Mandatory variables**

All networks must have an interface defined, as described in *Per-host Network Configuration*. By default the VMs are attached to the admin overcloud network. If, for example, admin\_oc\_net\_name was set to example\_net, you would need to define example\_net\_interface. It is possible to change the list of networks that a VM is attached to by modifying infra\_vm\_network\_interfaces. Additional interfaces can be added by setting infra\_vm\_network\_interfaces\_extra.

List of Kayobe applied defaults to required docker\_container variables. Any of these variables can be overridden with a host var.

```
→#
# Infrastructure VM configuration.
# Name of the infra VM.
infra_vm_name: "{{ inventory_hostname }}"
# Memory in MB.
infra_vm_memory_mb: "{{ 16 * 1024 }}"
# Number of vCPUs.
infra_vm_vcpus: 4
# List of volumes.
infra_vm_volumes:
 - "{{ infra_vm_root_volume }}"
   "{{ infra_vm_data_volume }}"
# Root volume.
infra_vm_root_volume:
 name: "{{ infra_vm_name }}-root"
 pool: "{{ infra_vm_pool }}"
 capacity: "{{ infra_vm_root_capacity }}"
 format: "{{ infra_vm_root_format }}"
 image: "{{ infra_vm_root_image }}"
# Data volume.
infra_vm_data_volume:
 name: "{{ infra_vm_name }}-data"
```

```
pool: "{{ infra_vm_pool }}"
 capacity: "{{ infra_vm_data_capacity }}"
  format: "{{ infra_vm_data_format }}"
# Name of the storage pool for the infra VM volumes.
infra_vm_pool: default
# Capacity of the infra VM root volume.
infra_vm_root_capacity: 50G
# Format of the infra VM root volume.
infra_vm_root_format: qcow2
# Base image for the infra VM root volume. Default is
# "https://cloud-images.ubuntu.com/noble/current/noble-server-cloudimg-amd64.
⇒img"
# when os_distribution is "ubuntu", or
# https://dl.rockylinux.org/pub/rocky/9/images/x86_64/Rocky-9-GenericCloud.
→latest.x86_64.qcow2
# when os_distribution is "rocky",
# or
# "https://cloud.centos.org/centos/9-stream/x86_64/images/Cent0S-Stream-
→ GenericCloud-9-20221206.0.x86_64.gcow2"
# otherwise.
infra_vm_root_image: >-
 https://cloud-images.ubuntu.com/noble/current/noble-server-cloudimg-amd64.
⇒imq
 {%- elif os_distribution == 'rocky' %}
→latest.x86_64.qcow2
→GenericCloud-9-20221206.0.x86_64.qcow2
 {%- endif %}
# Capacity of the infra VM data volume.
infra_vm_data_capacity: 100G
# Format of the infra VM data volume.
infra_vm_data_format: gcow2
# List of network interfaces to attach to the infra VM.
infra_vm_interfaces: "{{ network_interfaces | sort | map('net_libvirt_vm_
→network') | list }}"
# Hypervisor that the VM runs on.
infra_vm_hypervisor: "{{ groups['seed-hypervisor'] | first }}"
```

```
# Customise ansible_ssh_extra_args for the test that checks SSH connectivity
# after provisioning. Defaults to disabling ssh host key checking.
infra_vm_wait_connection_ssh_extra_args: '-o StrictHostKeyChecking=no'
# OS family. Needed for config drive generation.
infra_vm_os_family: "{{ 'RedHat' if os_distribution in ['centos', 'rocky']_
→else 'Debian' }}"
# Boot firmware. Possible values are 'bios' or 'efi'. Default is 'efi'.
infra_vm_boot_firmware: "efi"
# Machine type. Libvirt default configuration is used.
infra_vm_machine:
# Infrastructure VM node configuration.
# User with which to access the infrastructure vm via SSH during bootstrap, in
# order to setup the Kayobe user account. Default is {{ os_distribution }}.
infra_vm_bootstrap_user: "{{ os_distribution }}"
→#
# Infrastructure VM network interface configuration.
# List of networks to which infrastructure vm nodes are attached.
infra_vm_network_interfaces: >
 {{ (infra_vm_default_network_interfaces +
     infra_vm_extra_network_interfaces) | select | unique | list }}
# List of default networks to which infrastructure vm nodes are attached.
infra_vm_default_network_interfaces: >
 {{ [admin_oc_net_name] | select | unique | list }}
# List of extra networks to which infrastructure vm nodes are attached.
infra_vm_extra_network_interfaces: []
# Infrastructure VM node software RAID configuration.
# List of software RAID arrays. See mrlesmithjr.mdadm role for format.
infra_vm_mdadm_arrays: []
# Infrastructure VM node encryption configuration.
```

```
# List of block devices to encrypt. See stackhpc.luks role for format.
infra_vm_luks_devices: []
# Infrastructure VM node LVM configuration.
# List of infrastructure vm volume groups. See mrlesmithjr.manage_lvm role for
# format.
infra_vm_lvm_groups: "{{ infra_vm_lvm_groups_default + infra_vm_lvm_groups_
→extra }}"
# Default list of infrastructure vm volume groups. See mrlesmithjr.manage_lvm
# role for format.
infra_vm_lvm_groups_default: "{{ [infra_vm_lvm_group_data] if infra_vm_lvm_
→group_data_enabled | bool else [] }}"
# Additional list of infrastructure vm volume groups. See mrlesmithjr.manage_
\hookrightarrow 1 \text{vm}
# role for format.
infra_vm_lvm_groups_extra: []
# Whether a 'data' LVM volume group should exist on the infrastructure vm. By
# default this contains a 'docker-volumes' logical volume for Docker volume
# storage. Default is false.
infra_vm_lvm_group_data_enabled: false
# Infrastructure VM LVM volume group for data. See mrlesmithjr.manage_lvm role
# for format.
infra_vm_lvm_group_data:
 vgname: data
 disks: "{{ infra_vm_lvm_group_data_disks }}"
 create: True
 lvnames: "{{ infra_vm_lvm_group_data_lvs }}"
# List of disks for use by infrastructure vm LVM data volume group. Default to
# an invalid value to require configuration.
infra_vm_lvm_group_data_disks:
# List of LVM logical volumes for the data volume group.
infra_vm_lvm_group_data_lvs:
  - "{{ infra_vm_lvm_group_data_lv_docker_volumes }}"
# Docker volumes LVM backing volume.
infra_vm_lvm_group_data_lv_docker_volumes:
 lvname: docker-volumes
 size: "{{ infra_vm_lvm_group_data_lv_docker_volumes_size }}"
  create: True
```

```
filesystem: "{{ infra_vm_lvm_group_data_lv_docker_volumes_fs }}"
 mount: True
 mntp: /var/lib/docker/volumes
# Size of docker volumes LVM backing volume.
infra_vm_lvm_group_data_lv_docker_volumes_size: 75%VG
# Filesystem for docker volumes LVM backing volume. ext4 allows for shrinking.
infra_vm_lvm_group_data_lv_docker_volumes_fs: ext4
# Infrastructure VM node sysctl configuration.
# Dict of sysctl parameters to set.
infra_vm_sysctl_parameters: {}
<u></u>#
# Infrastructure VM node tuned configuration.
# Builtin tuned profile to use. Format is same as that used by giovtorres.
→tuned
# role. Default is virtual-guest.
infra_vm_tuned_active_builtin_profile: "virtual-guest"
# Infrastructure VM node user configuration.
# List of users to create. This should be in a format accepted by the
# singleplatform-eng.users role.
infra_vm_users: "{{ users_default }}"
# Infrastructure VM node firewalld configuration.
# Whether to install and enable firewalld.
infra_vm_firewalld_enabled: false
# A list of zones to create. Each item is a dict containing a 'zone' item.
infra_vm_firewalld_zones: []
# A firewalld zone to set as the default. Default is unset, in which case the
# default zone will not be changed.
infra_vm_firewalld_default_zone:
# A list of firewall rules to apply. Each item is a dict containing arguments
```

#### **Customisations**

Examples of common customisations are shown below.

By default the Ansible inventory name is used as the name of the VM. This may be overridden via infra\_vm\_name:

```
Listing 166: $KAYOBE_CONFIG_PATH/inventory/host_vars/
an-example-vm
```

```
# Name of the infra VM.
infra_vm_name: "the-special-one"
```

By default the VM has 16G of RAM. This may be changed via infra\_vm\_memory\_mb:

```
Listing 167: $KAYOBE_CONFIG_PATH/inventory/host_vars/
an-example-vm
```

```
# Memory in MB. Defaults to 16GB.
infra_vm_memory_mb: "{{ 8 * 1024 }}"
```

The default network configuration attaches infra VMs to the admin network. If this is not appropriate, modify infra\_vm\_network\_interfaces. At a minimum the network interface name for the network should be defined.

Listing 168: \$KAYOBE\_CONFIG\_PATH/inventory/host\_vars/
an-example-vm

```
# Network interfaces that the VM is attached to.
infra_vm_network_interfaces:
    - aio

# Mandatory: All networks must have an interface defined.
aio_interface: eth0

# By default kayobe will connect to a host via ``admin_oc_net``.
```

```
# As we have not attached this VM to this network, we must override
# ansible_host.
ansible_host: "{{ 'aio' | net_ip }}"
```

Configuration for all VMs can be set using extra\_vars defined in \$KAYOBE\_CONFIG\_PATH/infra-vms.yml. Note that normal Ansible precedence rules apply and the variables will override any host\_vars. If you need to override the defaults, but still maintain per-host settings, use group\_vars instead.

### Deploying the virtual machine

Once the initial configuration has been done follow the steps in *Infrastructure VMs*.

#### **Virtual GPUs**

Kayobe contains playbooks to configure virtualised GPUs on supported NVIDIA hardware. This allows you to statically create mdev devices that can be used by Nova to present a virtualised GPU to guest VMs. Known working GPUs are:

• NVIDIA A100

## **BIOS** configuration

## Intel

- Enable VT-x in the BIOS for virtualisation support.
- Enable VT-d in the BIOS for IOMMU support.

#### **AMD**

- Enable AMD-V in the BIOS for virtualisation support.
- Enable AMD-Vi in the BIOS for IOMMU support.

#### **Example: Dell**

Enabling SR-IOV with racadm:

```
/opt/dell/srvadmin/bin/idracadm7 set BIOS.IntegratedDevices.SriovGlobalEnable

→Enabled
/opt/dell/srvadmin/bin/idracadm7 jobqueue create BIOS.Setup.1-1
<reboot>
```

Enabling CPU Virtualization with *racadm*:

```
/opt/dell/srvadmin/bin/idracadm7 set BIOS.ProcSettings.ProcVirtualization

→Enabled
/opt/dell/srvadmin/bin/idracadm7 jobqueue create BIOS.Setup.1-1
<reboot>
```

# Obtain driver from NVIDIA licensing portal

Download NVIDIA GRID driver from here (This requires a login).

# Configuration

```
See also

For further context, please see:

• Kayobe Configuration
```

Add hosts with supported GPUs to the compute-vgpu group. If using bifrost and the kayobe overcloud inventory discover mechanism, this can be achieved with:

Listing 169: \$KAYOBE\_CONFIG\_PATH/overcloud.yml

```
overcloud_group_hosts_map:
    compute-vgpu:
        - "computegpu000"
```

Configure the location of the NVIDIA driver:

Listing 170: \$KAYOBE\_CONFIG\_PATH/vgpu.yml

```
---
vgpu_driver_url: "https://example.com/NVIDIA-GRID-Linux-KVM-525.105.14-525.

→105.17-528.89.zip"
```

If you dont know which vGPU types your card supports, these can be determined by following *NVIDIA* vGPU types.

You can then define <code>group\_vars</code> describing the vGPU configuration:

```
Listing 171: $KAYOBE_CONFIG_PATH/inventory/group_vars/compute-vgpu/vgpu
```

```
#nvidia-692 GRID A100D-4C

#nvidia-693 GRID A100D-8C

#nvidia-694 GRID A100D-10C

#nvidia-695 GRID A100D-16C

#nvidia-696 GRID A100D-20C

#nvidia-697 GRID A100D-40C

#nvidia-698 GRID A100D-80C
```

```
#nvidia-699 GRID A100D-1-10C
#nvidia-700 GRID A100D-2-20C
#nvidia-701 GRID A100D-3-40C
#nvidia-702 GRID A100D-4-40C
#nvidia-703 GRID A100D-7-80C
#nvidia-707 GRID A100D-1-10CME
vgpu_definitions:
  # Configuring a MIG backed VGPU
  pci_address: "0000:17:00.0"
   mia devices:
      # This section describes how to partition the card using MIG. The key
      # in the dictionary represents a MIG profile supported by your card and
      # the value is the number of MIG devices of that type that you want
      # to create. The vGPUS are then created on top of these MIG devices.
      # The available profiles can be found in the NVIDIA documentation:
      # https://docs.nvidia.com/grid/15.0/grid-vgpu-user-guide/index.html
→#virtual-gpu-types-grid-reference
      "1g.10gb": 1
      "2g.20gb": 3
   virtual_functions:
      # The mdev type is the NVIDIA identifier for a particular vGPU. When_
→using
     # MIG backed vGPUs these must match up with your MIG devices. See the
\rightarrow NVIDIA
      # vGPU types section in this document.
      - mdev_type: nvidia-700
       index: 0
      - mdev_type: nvidia-700
        index: 1
      - mdev_type: nvidia-700
        index: 2
       mdev_type: nvidia-699
        index: 3
  # Configuring a card in a time-sliced configuration (non-MIG backed)
   pci_address: "0000:65:00.0"
    virtual_functions:
       mdev_type: nvidia-697
        index: 0
      - mdev_type: nvidia-697
        index: 1
```

To apply this configuration, use:

```
(kayobe) $ kayobe overcloud host configure -t vgpu
```

## **NVIDIA vGPU types**

#### See also

For further context, please see:

- NVIDIA docs on vGPU types
- Kolla Ansible Configuration

The NVIDIA vGPU drivers must be installed to be able to query for the available vGPU types. This can be achieved by not defining any virtual functions in the vGPU definition:

```
Listing 172: $KAYOBE_CONFIG_PATH/inventory/group_vars/compute-vgpu/vgpu
```

```
vgpu_definitions:
    pci_address: "0000:17:00.0"
    virtual_functions: []
```

See *Configuration*. You can then use mdevctl to query for the available vGPU types.

```
mdevctl types
```

## **Kolla Ansible configuration**

#### See also

For further context, please see:

- Attaching virtual GPU devices to guests in the Nova documentation
- Kolla Ansible Configuration

To use the mdev devices that were created, modify nova.conf to add a list of mdev devices that can be passed through to guests:

Listing 173: \$KAYOBE\_CONFIG\_PATH/kolla/config/nova/nova-compute.conf

```
{% raw %}
{% if inventory_hostname in groups['compute-vgpu'] %}
[devices]
enabled_mdev_types = nvidia-700, nvidia-699, nvidia-697
[mdev_nvidia-700]
device_addresses = 0000:17:00.4,0000:17:00.5,0000:17:00.6
mdev_class = CUSTOM_NVIDIA_700
[mdev_nvidia-699]
device_addresses = 0000:17:00.7
mdev_class = CUSTOM_NVIDIA_699
```

```
[mdev_nvidia-697]
device_addresses = 0000:65:00.4,0000:65:00.5
mdev_class = CUSTOM_NVIDIA_697
{% endif %}
{% endraw %}
```

You will need to adjust the PCI addresses to match the virtual function addresses. These can be obtained by checking the mdevetl configuration after applying the *configuration*:

```
# mdevctl list
73269d0f-b2c9-438d-8f28-f9e4bc6c6995 0000:17:00.4 nvidia-700 manual (defined)
dc352ef3-efeb-4a5d-a48e-912eb230bc76 0000:17:00.5 nvidia-700 manual (defined)
a464fbae-1f89-419a-a7bd-3a79c7b2eef4 0000:17:00.6 nvidia-700 manual (defined)
f3b823d3-97c8-4e0a-ae1b-1f102dcb3bce 0000:17:00.7 nvidia-699 manual (defined)
330be289-ba3f-4416-8c8a-b46ba7e51284 0000:65:00.4 nvidia-700 manual (defined)
1ba5392c-c61f-4f48-8fb1-4c6b2bbb0673 0000:65:00.5 nvidia-700 manual (defined)
f6868020-eb3a-49c6-9701-6c93e4e3fa9c 0000:65:00.6 nvidia-700 manual (defined)
00501f37-c468-5ba4-8be2-8d653c4604ed 0000:65:00.7 nvidia-699 manual (defined)
```

The mdev\_class maps to a resource class that you can set in your flavor definition. Note that if you only define a single mdev type on a given hypervisor, then the mdev\_class configuration option is silently ignored and it will use the VGPU resource class (See bug 1943934).

To apply the configuration to Nova:

```
(kayobe) $ kayobe overcloud service deploy -kt nova
```

# **OpenStack flavors**

Define some flavors that request the resource class that was configured in nova.conf. An example definition, that can be used with openstack.cloud.compute\_flavor Ansible module, is shown below:

```
openstack.cloud.compute_flavor:
   name: "vgpu.a100.2g.20gb"
   ram: 65536
   disk: 30
   vcpus: 8
   is_public: false
   extra_specs:
     hw:cpu_policy: "dedicated"
     hw:cpu_thread_policy: "prefer"
     hw:mem_page_size: "1GB"
     hw:cpu_sockets: 2
     hw:numa_nodes: 8
     hw_rng:allowed: "True"
     resources:CUSTOM_NVIDIA_700: "1"
```

# **Changing VGPU device types**

Converting the second card to an NVIDIA-698 (whole card). The hypervisor should be empty so we can freely delete mdevs. If this is not the case you will need to check which mdevs are in use and use extreme caution. First clean up the mdev definitions to make room for the new device:

```
[stack@computegpu000 ~] $ sudo mdevctl list
5c630867-a673-5d75-aa31-a499e6c7cb19 0000:21:00.4 nvidia-697 manual (defined)
eaa6e018-308e-58e2-b351-aadbcf01f5a8 0000:21:00.5 nvidia-697 manual (defined)
72291b01-689b-5b7a-9171-6b3480deabf4 0000:81:00.4 nvidia-697 manual (defined)
0a47ffd1-392e-5373-8428-707a4e0ce31a 0000:81:00.5 nvidia-697 manual (defined)
stack@computegpu000 ~ \ sudo mdevctl stop --uuid 72291b01-689b-5b7a-9171-
\rightarrow6b3480deabf4
stack@computegpu000 ~ \ sudo mdevctl stop --uuid 0a47ffd1-392e-5373-8428-
→707a4e0ce31a
[stack@computegpu000 ~] $ sudo mdevctl undefine --uuid 0a47ffd1-392e-5373-8428-
→707a4e0ce31a
[stack@computegpu000 ~]$ sudo mdevctl undefine --uuid 72291b01-689b-5b7a-9171-
→6b3480deabf4
[stack@computegpu000 ~] $ sudo mdevctl list --defined
5c630867-a673-5d75-aa31-a499e6c7cb19 0000:21:00.4 nvidia-697 manual (active)
eaa6e018-308e-58e2-b351-aadbcf01f5a8 0000:21:00.5 nvidia-697 manual (active)
# We can re-use the first virtual function
```

Secondly remove the systemd unit that starts the mdev device:

```
[stack@computegpu000 ~]$ sudo rm /etc/systemd/system/multi-user.target.wants/

nvidia-mdev@0a47ffd1-392e-5373-8428-707a4e0ce31a.service

[stack@computegpu000 ~]$ sudo rm /etc/systemd/system/multi-user.target.wants/

nvidia-mdev@72291b01-689b-5b7a-9171-6b3480deabf4.service
```

Adapt your *Kayobe* and *Kolla Ansible* configuration to match the desired state and then re-run host configure:

```
(kayobe) $ kayobe overcloud host configure --tags vgpu --limit computegpu000
```

Check the result:

```
[stack@computegpu000 ~]$ mdevctl list

5c630867-a673-5d75-aa31-a499e6c7cb19 0000:21:00.4 nvidia-697 manual

eaa6e018-308e-58e2-b351-aadbcf01f5a8 0000:21:00.5 nvidia-697 manual

72291b01-689b-5b7a-9171-6b3480deabf4 0000:81:00.4 nvidia-698 manual
```

Reconfigure nova to match the change:

```
(kayobe) $ kayobe overcloud service reconfigure -kt nova --kolla-limit⊔

→computegpu000 --skip-prechecks
```

#### Nova cells

In the Train release, Kolla Ansible gained full support for the Nova cells v2 scale out feature. Whilst configuring Nova cells is documented in Kolla Ansible, implementing that configuration in Kayobe is documented here.

In Kolla Ansible, Nova cells are configured via group variables. In Kayobe, these group variables can be set via Kayobe configuration. For example, to configure cell0001 the following file could be created:

Listing 174: \$KAYOBE\_CONFIG\_PATH/kolla/inventory/group\_vars/cell0001/all

```
nova_cell_name: cell0001
nova_cell_novncproxy_group: cell0001-vnc
nova_cell_conductor_group: cell0001-control
nova_cell_compute_group: cell0001-compute
```

After defining the cell <code>group\_vars</code> the Kayobe inventory can be configured. In Kayobe, cell controllers and cell compute hosts become part of the existing <code>controllers</code> and <code>compute</code> Kayobe groups because typically they will need to be provisioned in the same way. In Kolla Ansible, to prevent non-cell services being mapped to cell controllers, the <code>controllers</code> group must be split into two. The inventory file should also include the cell definitions. The following groups and hosts files give an example of how this may be achieved:

Listing 175: \$KAYOBE\_CONFIG\_PATH/inventory/groups

(continues on next page)

```
# Add controllers to network group by default for backwards compatibility,
# although they could be separate hosts.
# Empty group to provide declaration of monitoring group.
# Empty group to provide declaration of storage group.
# Empty group to provide declaration of compute group.
# Empty group to provide declaration of top-level controllers.
# Docker groups.
# Hosts in this group will have Docker installed.
# Hosts in this group will have a Docker Registry deployed. This group should
# generally contain only a single host, to avoid deploying multiple.
→independent
# registries which may become unsynchronized.
# Baremetal compute node groups.
# Empty group to provide declaration of baremetal-compute group.
```

(continues on next page)

# Listing 176: \$KAYOBE\_CONFIG\_PATH/inventory/hosts

```
# Kayobe hosts inventory file. This file should be modified to define the hosts
# and their top-level group membership.

# This host acts as the configuration management Ansible control host. This must be
# localhost.
localhost ansible_connection=local

[seed-hypervisor]
# Add a seed hypervisor node here if required. This host will run a seed node
# Virtual Machine.

[seed]
operator

[controllers:children]
top-level-controllers
cell-controllers
[top-level-controllers]
control01

[cell-controllers:children]
cell01-control
cell02-control
[compute:children]
```

(continues on next page)

```
# Add management network switches here if required.
# Add control and provisioning switches here if required.
# Add high speed switches here if required.
```

Having configured the Kayobe inventory, the Kolla Ansible inventory can be configured. Currently this can be done via the kolla\_overcloud\_inventory\_top\_level\_group\_map variable. For example, to configure the two cells defined in the Kayobe inventory above, the variable could be set to the following:

Listing 177: \$KAYOBE\_CONFIG\_PATH/kolla.yml

```
kolla_overcloud_inventory_top_level_group_map:
  control:
    groups:
 network:
    groups:
  compute:
    groups:
 monitoring:
    groups:
  cell-control:
    groups:
  cel10001:
    groups:
  cell0001-control:
     groups:
  cell0001-compute:
    groups:
  cell0001-vnc:
    groups:
  cel10002:
    groups:
  cell0002-control:
    groups:
  cell0002-compute:
    groups:
  cell0002-vnc:
    groups:
```

Finally, Nova cells can be enabled in Kolla Ansible:

Listing 178: \$KAYOBE\_CONFIG\_PATH/kolla/globals.yml

enable\_cells: True

# 3.7 Deployment

This section describes usage of Kayobe to install an OpenStack cloud onto a set of bare metal servers. We assume access is available to a node which will act as the hypervisor hosting the seed node in a VM. We also assume that this seed hypervisor has access to the bare metal nodes that will form the OpenStack control plane. Finally, we assume that the control plane nodes have access to the bare metal nodes that will form the workload node pool.

#### See also

Information on the configuration of a Kayobe environment is available *here*.

### 3.7.1 Ansible Control Host

Before starting deployment we must bootstrap the Ansible control host. Tasks performed here include:

- Install required Ansible roles from Ansible Galaxy.
- Generate an SSH key if necessary and add it to the current users authorised keys.
- Install Kolla Ansible locally at the configured version.

To bootstrap the Ansible control host:

(kayobe) \$ kayobe control host bootstrap

# 3.7.2 Physical Network

The physical network can be managed by Kayobe, which uses Ansibles network modules. Currently the most popular switches for cloud infrastructure are supported but this could easily be extended. To provision the physical network:

```
(kayobe) $ kayobe physical network configure --group <group> [--enable-
→discovery]
```

The --group argument is used to specify an Ansible group containing the switches to be configured.

The --enable-discovery argument enables a one-time configuration of ports attached to baremetal compute nodes to support hardware discovery via ironic inspector.

It is possible to limit the switch interfaces that will be configured, either by interface name or interface description:

The names or descriptions should be separated by commas. This may be useful when adding compute nodes to an existing deployment, in order to avoid changing the configuration interfaces in use by active nodes.

The --display argument will display the candidate switch configuration, without actually applying it.

### See also

Information on configuration of physical network devices is available *here*.

# 3.7.3 Seed Hypervisor

#### Note

It is not necessary to run the seed services in a VM. To use an existing bare metal host or a VM provisioned outside of Kayobe, this section may be skipped.

# **Host Configuration**

To configure the seed hypervisors host OS, and the Libvirt/KVM virtualisation support:

(kayobe) \$ kayobe seed hypervisor host configure

## See also

Information on configuration of hosts is available here.

# 3.7.4 Seed

# **VM Provisioning**

#### Note

It is not necessary to run the seed services in a VM. To use an existing bare metal host or a VM provisioned outside of Kayobe, this step may be skipped. Ensure that the Ansible inventory contains a host for the seed.

The seed hypervisor should have CentOS or Rocky or Ubuntu with libvirt installed. It should have libvirt networks configured for all networks that the seed VM needs access to and a libvirt storage pool available for the seed VMs volumes. To provision the seed VM:

3.7. Deployment 149

(kayobe) \$ kayobe seed vm provision

When this command has completed the seed VM should be active and accessible via SSH. Kayobe will update the Ansible inventory with the IP address of the VM.

# **Host Configuration**

To configure the seed host OS:

(kayobe) \$ kayobe seed host configure

#### Note

If the seed host uses disks that have been in use in a previous installation, it may be necessary to wipe partition and LVM data from those disks. To wipe all disks that are not mounted during host configuration:

(kayobe) \$ kayobe seed host configure --wipe-disks

#### See also

Information on configuration of hosts is available *here*.

### **Building Container Images**

## Note

It is possible to use prebuilt container images from an image registry such as Quay.io. In this case, this step can be skipped.

It is possible to use prebuilt container images from an image registry such as Quay.io. In some cases it may be necessary to build images locally either to apply local image customisation or to use a downstream version of kolla. Images are built by hosts in the container-image-builders group, which by default includes the seed.

To build container images:

(kayobe) \$ kayobe seed container image build

It is possible to build a specific set of images by supplying one or more image name regular expressions:

(kayobe) \$ kayobe seed container image build bifrost-deploy

In order to push images to a registry after they are built, add the --push argument.

#### See also

Information on configuration of Kolla for building container images is available here.

### **Deploying Containerised Services**

At this point the seed services need to be deployed on the seed VM. These services are deployed in the bifrost\_deploy container.

This command will also build the Operating System image that will be used to deploy the overcloud nodes using Disk Image Builder (DIB), if overcloud\_dib\_build\_host\_images is set to False.

#### Note

If you are using Rocky Linux - building of the Operating System image needs to be done using kayobe overcloud host image build.

To deploy the seed services in containers:

(kayobe) \$ kayobe seed service deploy

After this command has completed the seed services will be active.

#### Note

Bifrost deployment behaviour is split between Kayobe and Kolla-Ansible. As such, you should use both --tags kolla-bifrost and --kolla-tags bifrost if you want to limit to Bifrost deployment.

## See also

Information on configuration of Kolla Ansible is available *here*. See *here* for information about configuring Bifrost. *Overcloud root disk image configuration* provides information on configuring the root disk image build process. See *here* for information about deploying additional, custom services (containers) on a seed node.

### **Building Deployment Images**

# Note

It is possible to use prebuilt deployment images. In this case, this step can be skipped.

It is possible to use prebuilt deployment images from the OpenStack hosted tarballs or another source. In some cases it may be necessary to build images locally either to apply local image customisation or to use a downstream version of Ironic Python Agent (IPA). In order to build IPA images, the ipa\_build\_images variable should be set to True.

3.7. Deployment 151

# kayobe Documentation, Release 17.3.1.dev5

To build images locally:

(kayobe) \$ kayobe seed deployment image build

If images have been built previously, they will not be rebuilt. To force rebuilding images, use the --force-rebuild argument.

#### See also

See *here* for information on how to configure the IPA image build process.

# **Building Overcloud Host Disk Images**

#### Note

This step is only relevant if overcloud\_dib\_build\_host\_images is set to True, which is the default since the Zed release.

Host disk images are deployed on overcloud hosts during provisioning. To build host disk images:

(kayobe) \$ kayobe overcloud host image build

If images have been built previously, they will not be rebuilt. To force rebuilding images, use the --force-rebuild argument.

#### See also

See *here* for information on how to configure the overcloud host disk image build process.

## Accessing the Seed via SSH (Optional)

For SSH access to the seed, first determine the seeds IP address. We can use the kayobe configuration dump command to inspect the seeds IP address:

(kayobe) \$ kayobe configuration dump --host seed --var-name ansible\_host

The kayobe\_ansible\_user variable determines which user account will be used by Kayobe when accessing the machine via SSH. By default this is stack. Use this user to access the seed:

\$ ssh <kayobe ansible user>@<seed VM IP>

To see the active Docker containers:

\$ docker ps

Leave the seed VM and return to the shell on the Ansible control host:

\$ exit

### 3.7.5 Infrastructure VMs

# Warning

Support for infrastructure VMs is considered experimental: its design may change in future versions without a deprecation period.

# Note

It necessary to perform some configuration before these steps can be followed. Please see *Infrastructure VMs*.

### **VM Provisioning**

The hypervisor used to host a VM is controlled via the infra\_vm\_hypervisor variable. It defaults to use the seed hypervisor. All hypervisors should have CentOS or Ubuntu with libvirt installed. It should have libvirt networks configured for all networks that the VM needs access to and a libvirt storage pool available for the VMs volumes. The steps needed for for the *seed* and the *seed hypervisor* can be found above.

To provision the infra VMs:

(kayobe) \$ kayobe infra vm provision

When this command has completed the infra VMs should be active and accessible via SSH. Kayobe will update the Ansible inventory with the IP address of the VM.

### **Host Configuration**

To configure the infra VM host OS:

(kayobe) \$ kayobe infra vm host configure

# Note

If the infra VM host uses disks that have been in use in a previous installation, it may be necessary to wipe partition and LVM data from those disks. To wipe all disks that are not mounted during host configuration:

(kayobe) \$ kayobe infra vm host configure --wipe-disks

3.7. Deployment 153

### See also

Information on configuration of hosts is available *here*.

## Using Hooks to deploy services on the VMs

A no-op service deployment command is provided to perform additional configuration. The intention is for users to define *hooks to custom playbooks* that define any further configuration or service deployment necessary.

To trigger the hooks:

```
(kayobe) $ kayobe infra vm service deploy
```

## **Example**

In this example we have an infra VM host called dns01 that provides DNS services. The host could be added to a dns-servers group in the inventory:

Listing 179: \$KAYOBE\_CONFIG\_PATH/inventory/infra-vms

```
[dns-servers]
an-example-vm
[infra-vms:children]
dns-servers
```

We have a custom playbook targeting the dns-servers group that sets up the DNS server:

Listing 180: \$KAYOBE\_CONFIG\_PATH/ansible/dns-server.yml

```
---
- name: Deploy DNS servers
hosts: dns-servers
tasks:
- name: Install bind packages
package:
name:
- bind
- bind-utils
become: true
```

Finally, we add a symlink to set up the playbook as a hook for the kayobe infra vm service deploy command:

```
(kayobe) $ mkdir -p ${KAYOBE_CONFIG_PATH}/hooks/infra-vm-host-configure/post.d
(kayobe) $ cd ${KAYOBE_CONFIG_PATH}/hooks/infra-vm-host-configure/post.d
(kayobe) $ ln -s ../../ansible/dns-server.yml 50-dns-server.yml
```

### 3.7.6 Overcloud

## **Discovery**

#### Note

If discovery of the overcloud is not possible, a static inventory of servers using the bifrost servers.yml file format may be configured using the kolla\_bifrost\_servers variable in \${KAYOBE\_CONFIG\_PATH}/bifrost.yml.

Discovery of the overcloud is supported by the ironic inspector service running in the bifrost\_deploy container on the seed. The service is configured to PXE boot unrecognised MAC addresses with an IPA ramdisk for introspection. If an introspected node does not exist in the ironic inventory, ironic inspector will create a new entry for it.

Discovery of the overcloud is triggered by causing the nodes to PXE boot using a NIC attached to the overcloud provisioning network. For many servers this will be the factory default and can be performed by powering them on.

On completion of the discovery process, the overcloud nodes should be registered with the ironic service running in the seed hosts bifrost\_deploy container. The node inventory can be viewed by executing the following on the seed:

```
$ docker exec -it bifrost_deploy bash
(bifrost_deploy) $ export OS_CLOUD=bifrost
(bifrost_deploy) $ baremetal node list
```

In order to interact with these nodes using Kayobe, run the following command to add them to the Kayobe and Kolla-Ansible inventories:

```
(kayobe) $ kayobe overcloud inventory discover
```

#### See also

This blog post provides a case study of the discovery process, including automatically naming Ironic nodes via switch port descriptions, Ironic Inspector and LLDP.

#### **Saving Hardware Introspection Data**

If ironic inspector is in use on the seed host, introspection data will be stored in the local nginx service. This data may be saved to the control host:

```
(kayobe) $ kayobe overcloud introspection data save
```

- --output-dir may be used to specify the directory in which introspection data files will be saved.
- --output-format may be used to set the format of the files.

3.7. Deployment 155

## **BIOS and RAID Configuration**

#### Note

BIOS and RAID configuration may require one or more power cycles of the hardware to complete the operation. These will be performed automatically.

#### Note

Currently, BIOS and RAID configuration of overcloud hosts is supported for Dell servers only.

Configuration of BIOS settings and RAID volumes is currently performed out of band as a separate task from hardware provisioning. To configure the BIOS and RAID:

```
(kayobe) $ kayobe overcloud bios raid configure
```

After configuring the nodes RAID volumes it may be necessary to perform hardware inspection of the nodes to reconfigure the ironic nodes scheduling properties and root device hints. To perform manual hardware inspection:

```
(kayobe) $ kayobe overcloud hardware inspect
```

There are currently a few limitations to configuring BIOS and RAID:

- The Ansible control host must be able to access the BMCs of the servers being configured.
- The Ansible control host must have the python-dracclient Python module available to the Python interpreter used by Ansible. The path to the Python interpreter is configured via ansible\_python\_interpreter.

# **Provisioning**

#### Note

There is a cloud-init issue which prevents Ironic nodes without names from being accessed via SSH after provisioning. To avoid this issue, ensure that all Ironic nodes in the Bifrost inventory are named. This may be achieved via *autodiscovery*, or manually, e.g. from the seed:

```
$ docker exec -it bifrost_deploy bash
(bifrost_deploy) $ export OS_CLOUD=bifrost
(bifrost_deploy) $ baremetal node set ee77b4ca-8860-4003-a18f-b00d01295bda -
→-name controller0
```

Provisioning of the overcloud is performed by the ironic service running in the bifrost container on the seed. To provision the overcloud nodes:

```
(kayobe) $ kayobe overcloud provision
```

After this command has completed the overcloud nodes should have been provisioned with an OS image. The command will wait for the nodes to become active in ironic and accessible via SSH.

# **Host Configuration**

To configure the overcloud hosts OS:

(kayobe) \$ kayobe overcloud host configure

#### Note

If the controller hosts use disks that have been in use in a previous installation, it may be necessary to wipe partition and LVM data from those disks. To wipe all disks that are not mounted during host configuration:

(kayobe) \$ kayobe overcloud host configure --wipe-disks

#### See also

Information on configuration of hosts is available here.

# **Building Container Images**

#### Note

It is possible to use prebuilt container images from an image registry such as Quay.io. In this case, this step can be skipped.

In some cases it may be necessary to build images locally either to apply local image customisation or to use a downstream version of kolla. Images are built by hosts in the container-image-builders group, which by default includes the seed. If no seed host is in use, for example in an all-in-one controller development environment, this group may be modified to cause containers to be built on the controllers.

To build container images:

(kayobe) \$ kayobe overcloud container image build

It is possible to build a specific set of images by supplying one or more image name regular expressions:

(kayobe) \$ kayobe overcloud container image build ironic- nova-api

When your environment uses OVN, OVS images will not be built. If you want to build all Neutron images at the same time, extra variable kolla\_build\_neutron\_ovs needs to be set to true:

3.7. Deployment 157

# kayobe Documentation, Release 17.3.1.dev5

In order to push images to a registry after they are built, add the --push argument.

#### See also

Information on configuration of Kolla for building container images is available *here*.

# **Pulling Container Images**

#### Note

It is possible to build container images locally avoiding the need for an image registry such as Quay.io. In this case, this step can be skipped.

In most cases suitable prebuilt kolla images will be available on Quay.io. The openstack.kolla organisation provides image repositories suitable for use with kayobe and will be used by default. To pull images from the configured image registry:

(kayobe) \$ kayobe overcloud container image pull

# **Building Deployment Images**

#### Note

It is possible to use prebuilt deployment images. In this case, this step can be skipped.

#### Note

Deployment images are only required for the overcloud when Ironic is in use. Otherwise, this step can be skipped.

It is possible to use prebuilt deployment images from the OpenStack hosted tarballs or another source. In some cases it may be necessary to build images locally either to apply local image customisation or to use a downstream version of Ironic Python Agent (IPA). In order to build IPA images, the ipa\_build\_images variable should be set to True.

To build images locally:

# (kayobe) \$ kayobe overcloud deployment image build

If images have been built previously, they will not be rebuilt. To force rebuilding images, use the --force-rebuild argument.

#### See also

See *here* for information on how to configure the IPA image build process.

# **Building Swift Rings**

#### Note

This section can be skipped if Swift is not in use.

Swift uses ring files to control placement of data across a cluster. These files can be generated automatically using the following command:

(kayobe) \$ kayobe overcloud swift rings generate

# **Deploying Containerised Services**

To deploy the overcloud services in containers:

(kayobe) \$ kayobe overcloud service deploy

Once this command has completed the overcloud nodes should have OpenStack services running in Docker containers.

#### See also

Information on configuration of Kolla Ansible is available here.

## Interacting with the Control Plane

Kolla-ansible writes out an environment file that can be used to access the OpenStack admin endpoints as the admin user:

```
$ source ${KOLLA_CONFIG_PATH:-/etc/kolla}/admin-openrc.sh
```

Kayobe also generates an environment file that can be used to access the OpenStack public endpoints as the admin user which may be required if the admin endpoints are not available from the Ansible control host:

\$ source \${KOLLA\_CONFIG\_PATH:-/etc/kolla}/public-openrc.sh

# **Performing Post-deployment Configuration**

To perform post deployment configuration of the overcloud services:

```
(kayobe) $ source ${KOLLA_CONFIG_PATH:-/etc/kolla}/admin-openrc.sh
(kayobe) $ kayobe overcloud post configure
```

This will perform the following tasks:

• Register Ironic Python Agent (IPA) images with glance

3.7. Deployment 159

- Register introspection rules with ironic inspector
- Register a provisioning network and subnet with neutron
- Configure Grafana organisations, dashboards and datasources

# 3.8 Upgrading

This section describes how to upgrade from one OpenStack release to another.

# 3.8.1 Preparation

Before you start, be sure to back up any local changes, configuration, and data.

# **Migrating Kayobe Configuration**

Kayobe configuration options may be changed between releases of kayobe. Ensure that all site local configuration is migrated to the target version format. If using the kayobe-config git repository to manage local configuration, this process can be managed via git. For example, to fetch version 1.0.0 of the configuration from the origin remote and merge it into the current branch:

```
$ git fetch origin 1.0.0
$ git merge 1.0.0
```

The configuration should be manually inspected after the merge to ensure that it is correct. Any new configuration options may be set at this point. In particular, the following options may need to be changed if not using their default values:

- kolla\_openstack\_release
- kolla\_tag
- kolla\_sources
- kolla\_build\_blocks
- kolla\_build\_customizations

Once the configuration has been migrated, it is possible to view the global variables for all hosts:

```
(kayobe) $ kayobe configuration dump
```

The output of this command is a JSON object mapping hosts to their configuration. The output of the command may be restricted using the --host, --hosts, --var-name and --dump-facts options.

If using the kayobe-env environment file in kayobe-config, this should also be inspected for changes and modified to suit the local ansible control host environment if necessary. When ready, source the environment file:

```
$ source kayobe-env
```

The Kayobe release notes provide information on each new release. In particular, the *Upgrade Notes* and *Deprecation Notes* sections provide information that might affect the configuration migration.

All changes made to the configuration should be committed and pushed to the hosting git repository.

# 3.8.2 Updating Kayobe Configuration

Ensure that the Kayobe configuration is checked out at the required commit.

First, ensure that there are no uncommitted local changes to the repository:

```
$ cd <base_path>/src/kayobe-config/
$ git status
```

Pull down changes from the hosting repository. For example, to fetch changes from the master branch of the origin remote:

```
$ git checkout master
$ git pull --ff-only origin master
```

Adjust this procedure to suit your environment.

# 3.8.3 Upgrading Kayobe

If a new, suitable version of kayobe is available, it should be installed. As described in *Installation*, Kayobe can be installed via the released Python packages on PyPI, or from source. Installation from a Python package is supported from Kayobe 5.0.0 onwards.

Kayobe supports skip-level (SLURP) upgrades, see the Kolla Ansible docs for details.

# **Upgrading from PyPI**

This section describes how to upgrade Kayobe from a Python package in a virtualenv. This is supported from Kayobe 5.0.0 onwards.

Ensure that the virtualenv is activated:

```
$ source <base_path>/venvs/kayobe/bin/activate
```

Update the pip package:

```
(kayobe) $ pip install -U pip
```

### Note

When updating Ansible above version 2.9.x, first uninstall it with pip uninstall ansible. A newer version will be installed with the next command, as a Kayobe dependency. If Ansible 2.10.x was installed and you want to use a newer version, also uninstall the ansible-base package with pip uninstall ansible-base.

If upgrading to the latest version of Kayobe:

```
(kayobe) $ pip install -U kayobe
```

Alternatively, to upgrade to a specific release of Kayobe:

3.8. Upgrading 161

```
(kayobe) $ pip install kayobe==5.0.0
```

# **Upgrading from source**

This section describes how to install Kayobe from source in a virtualenv.

First, check out the required version of the Kayobe source code. This may be done by pulling down the new version from opendev.org. Make sure that any local changes to kayobe are committed and merged with the new upstream code as necessary. For example, to pull version 5.0.0 from the origin remote:

```
$ cd <base_path>/src/kayobe
$ git pull origin 5.0.0
```

Ensure that the virtualenv is activated:

```
$ source <base_path>/venvs/kayobe/bin/activate
```

Update the pip package:

```
(kayobe) $ pip install -U pip
```

If using a non-editable install of Kayobe:

```
(kayobe) $ cd <base_path>/src/kayobe
(kayobe) $ pip install -U .
```

Alternatively, if using an editable install of Kayobe (version 5.0.0 onwards, see *Editable source installation* for details):

```
(kayobe) $ cd <base_path>/src/kayobe
(kayobe) $ pip install -U -e .
```

### 3.8.4 Upgrading the Ansible Control Host

Before starting the upgrade we must upgrade the Ansible control host. Tasks performed here include:

- Install updated Ansible role dependencies from Ansible Galaxy.
- Generate an SSH key if necessary and add it to the current users authorised keys.
- Upgrade Kolla Ansible locally to the configured version.

To upgrade the Ansible control host:

```
(kayobe) $ kayobe control host upgrade
```

# 3.8.5 Upgrading the Seed Hypervisor

Currently, upgrading the seed hypervisor services is not supported. It may however be necessary to upgrade host packages and some host services.

## **Upgrading Host Packages**

Prior to upgrading the seed hypervisor, it may be desirable to upgrade system packages on the seed hypervisor host.

To update all eligible packages, use \*, escaping if necessary:

```
(kayobe) $ kayobe seed hypervisor host package update --packages "*"
```

To only install updates that have been marked security related:

```
(kayobe) $ kayobe seed hypervisor host package update --packages "*" --

⇒security
```

# **Upgrading Host Services**

It may be necessary to upgrade some host services:

```
(kayobe) $ kayobe seed hypervisor host upgrade
```

Note that this will not perform full configuration of the host, and will instead perform a targeted upgrade of specific services where necessary.

# 3.8.6 Upgrading the Seed

The seed services are upgraded in two steps. First, new container images should be obtained either by building them locally or pulling them from an image registry. Second, the seed services should be replaced with new containers created from the new container images.

#### **Upgrading Host Packages**

Prior to upgrading the seed, it may be desirable to upgrade system packages on the seed host.

To update all eligible packages, use \*, escaping if necessary:

```
(kayobe) $ kayobe seed host package update --packages "*"
```

To only install updates that have been marked security related:

```
(kayobe) $ kayobe seed host package update --packages "*" --security
```

Note that these commands do not affect packages installed in containers, only those installed on the host.

3.8. Upgrading 163

# **Building Ironic Deployment Images**

#### Note

It is possible to use prebuilt deployment images. In this case, this step can be skipped.

It is possible to use prebuilt deployment images from the OpenStack hosted tarballs or another source. In some cases it may be necessary to build images locally either to apply local image customisation or to use a downstream version of Ironic Python Agent (IPA). In order to build IPA images, the ipa\_build\_images variable should be set to True. To build images locally:

(kayobe) \$ kayobe seed deployment image build

To overwrite existing images, add the --force-rebuild argument.

## **Upgrading Host Services**

It may be necessary to upgrade some host services:

(kayobe) \$ kayobe seed host upgrade

Note that this will not perform full configuration of the host, and will instead perform a targeted upgrade of specific services where necessary.

# **Building Container Images**

#### Note

It is possible to use prebuilt container images from an image registry such as Quay.io. In this case, this step can be skipped.

In some cases it may be necessary to build images locally either to apply local image customisation or to use a downstream version of kolla. To build images locally:

(kayobe) \$ kayobe seed container image build

In order to push images to a registry after they are built, add the --push argument.

# **Upgrading Containerised Services**

Containerised seed services may be upgraded by replacing existing containers with new containers using updated images which have been pulled from a registry or built locally.

To upgrade the containerised seed services:

(kayobe) \$ kayobe seed service upgrade

# 3.8.7 Upgrading the Overcloud

The overcloud services are upgraded in two steps. First, new container images should be obtained either by building them locally or pulling them from an image registry. Second, the overcloud services should be replaced with new containers created from the new container images.

# **Upgrading Host Packages**

Prior to upgrading the OpenStack control plane, it may be desirable to upgrade system packages on the overcloud hosts.

To update all eligible packages, use \*, escaping if necessary:

```
(kayobe) $ kayobe overcloud host package update --packages "*"
```

To only install updates that have been marked security related:

```
(kayobe) $ kayobe overcloud host package update --packages "*" --security
```

Note that these commands do not affect packages installed in containers, only those installed on the host.

# **Upgrading Host Services**

Prior to upgrading the OpenStack control plane, the overcloud host services should be upgraded:

```
(kayobe) $ kayobe overcloud host upgrade
```

Note that this will not perform full configuration of the host, and will instead perform a targeted upgrade of specific services where necessary.

### **Building Ironic Deployment Images**

# Note

It is possible to use prebuilt deployment images. In this case, this step can be skipped.

It is possible to use prebuilt deployment images from the OpenStack hosted tarballs or another source. In some cases it may be necessary to build images locally either to apply local image customisation or to use a downstream version of Ironic Python Agent (IPA). In order to build IPA images, the ipa\_build\_images variable should be set to True. To build images locally:

```
(kayobe) $ kayobe overcloud deployment image build
```

To overwrite existing images, add the --force-rebuild argument.

3.8. Upgrading 165

## **Upgrading Ironic Deployment Images**

Prior to upgrading the OpenStack control plane you should upgrade the deployment images. If you are using prebuilt images, update the following variables in etc/kayobe/ipa.yml accordingly:

- ipa\_kernel\_upstream\_url
- ipa\_kernel\_checksum\_url
- ipa\_kernel\_checksum\_algorithm
- ipa\_ramdisk\_upstream\_url
- ipa\_ramdisk\_checksum\_url
- ipa\_ramdisk\_checksum\_algorithm

Alternatively, you can update the files that the URLs point to. If building the images locally, follow the process outlined in *Building Ironic Deployment Images*.

To get Ironic to use an updated set of overcloud deployment images, you can run:

(kayobe) \$ kayobe baremetal compute update deployment image

This will register the images in Glance and update the deploy\_ramdisk and deploy\_kernel properties of the Ironic nodes.

Before rolling out the update to all nodes, it can be useful to test the image on a limited subset. To do this, you can use the baremetal-compute-limit option. See *Update Deployment Image* for more details.

### **Building Container Images**

#### Note

It is possible to use prebuilt container images from an image registry such as Quay.io. In this case, this step can be skipped.

In some cases it may be necessary to build images locally either to apply local image customisation or to use a downstream version of kolla. To build images locally:

(kayobe) \$ kayobe overcloud container image build

It is possible to build a specific set of images by supplying one or more image name regular expressions:

(kayobe) \$ kayobe overcloud container image build ironic- nova-api

In order to push images to a registry after they are built, add the --push argument.

# **Pulling Container Images**

#### Note

It is possible to build container images locally avoiding the need for an image registry such as Quay.io. In this case, this step can be skipped.

In most cases suitable prebuilt kolla images will be available on Quay.io. The openstack.kolla organisation provides image repositories suitable for use with kayobe and will be used by default. To pull images from the configured image registry:

(kayobe) \$ kayobe overcloud container image pull

## **Saving Overcloud Service Configuration**

It is often useful to be able to save the configuration of the control plane services for inspection or comparison with another configuration set prior to a reconfiguration or upgrade. This command will gather and save the control plane configuration for all hosts to the Ansible control host:

(kayobe) \$ kayobe overcloud service configuration save

The default location for the saved configuration is \$PWD/overcloud-config, but this can be changed via the output-dir argument. To gather configuration from a directory other than the default /etc/kolla, use the node-config-dir argument.

# **Generating Overcloud Service Configuration**

Prior to deploying, reconfiguring, or upgrading a control plane, it may be useful to generate the configuration that will be applied, without actually applying it to the running containers. The configuration should typically be generated in a directory other than the default configuration directory of /etc/kolla, to avoid overwriting the active configuration:

The configuration will be generated remotely on the overcloud hosts in the specified directory, with one subdirectory per container. This command may be followed by kayobe overcloud service configuration save to gather the generated configuration to the Ansible control host.

### **Upgrading Containerised Services**

Containerised control plane services may be upgraded by replacing existing containers with new containers using updated images which have been pulled from a registry or built locally.

To upgrade the containerised control plane services:

(kayobe) \$ kayobe overcloud service upgrade

It is possible to specify tags for Kayobe and/or kolla-ansible to restrict the scope of the upgrade:

3.8. Upgrading 167

# 3.9 Administration

This section describes how to use kayobe to simplify post-deployment administrative tasks.

# 3.9.1 General Administration

# **Updating the Control Host**

There are several pieces of software and configuration that must be installed and synchronised on the Ansible Control host:

- Kayobe configuration
- Kayobe Python package
- Ansible Galaxy roles
- Kolla Ansible Python package

A change to the configuration may require updating the Kolla Ansible Python package. Updating the Kayobe Python package may require updating the Ansible Galaxy roles. Its not always easy to know which of these are required, so the simplest option is to apply all of the following steps when any of the above are changed.

- 1. Update Kayobe configuration to the required commit
- 2. *Upgrade the Kayobe Python package* to the required version
- 3. *Upgrade the Ansible control host* to synchronise the Ansible Galaxy roles and Kolla Ansible Python package.

# **Running Kayobe Playbooks on Demand**

In some situations it may be necessary to run an individual Kayobe playbook. Playbooks are stored in <kayobe repo>/ansible/\*.yml. To run an arbitrary Kayobe playbook:

```
(kayobe) $ kayobe playbook run <playbook> [<playbook>]
```

### **Running Kolla-ansible Commands**

To execute a kolla-ansible command:

(kayobe) \$ kayobe kolla ansible run <command>

# **Dumping Kayobe Configuration**

The Ansible configuration space is quite large, and it can be hard to determine the final values of Ansible variables. We can use Kayobes configuration dump command to view individual variables or the variables for one or more hosts. To dump Kayobe configuration for one or more hosts:

### (kayobe) \$ kayobe configuration dump

The output is a JSON-formatted object mapping hosts to their hostvars.

We can use the --var-name argument to inspect a particular variable or the --host or --hosts arguments to view a variable or variables for a specific host or set of hosts.

### **Checking Network Connectivity**

In complex networking environments it can be useful to be able to automatically check network connectivity and diagnose networking issues. To perform some simple connectivity checks:

### (kayobe) \$ kayobe network connectivity check

Note that this will run on the seed, seed hypervisor, and overcloud hosts. If any of these hosts are not expected to be active (e.g. prior to overcloud deployment), the set of target hosts may be limited using the --limit argument.

These checks will attempt to ping the external IP address 8.8.8.8 and external hostname google. com. They can be configured with the nc\_external\_ip and nc\_external\_hostname variables in \$KAYOBE\_CONFIG\_PATH/networks.yml.

## 3.9.2 Seed Administration

# **Deprovisioning The Seed VM**

#### Note

This step will destroy the seed VM and its data volumes.

To deprovision the seed VM:

(kayobe) \$ kayobe seed vm deprovision

## Destroying all services on the seed

## Warning

This step will destroy all containers, container images, and volumes that were deployed by Kayobe and Kolla. To destroy volumes and images associated with *custom containers*, you must configure the

3.9. Administration 169

post\_destroy and pre\_destroy hooks to do the clean up manually as Kayobe will not automatically clean these up. It is generally only advised to run this command when you have no important data on the system.

To destroy the seed services:

```
(kayobe) $ kayobe seed service destroy --yes-i-really-really-mean-it
```

This can optionally be used with a tag:

```
(kayobe) \ kayobe seed service destroy --yes-i-really-really-mean-it -kt none_ \hookrightarrow-t docker-registry
```

Care must be taken to set both kayobe and kolla tags to avoid accidentally destroying other services.

# **Updating Packages**

It is possible to update packages on the seed host.

# **Package Repositories**

If using custom DNF package repositories on CentOS or Rocky, it may be necessary to update these prior to running a package update. To do this, update the configuration in \${KAYOBE\_CONFIG\_PATH}/dnf. yml and run the following command:

```
(kayobe) $ kayobe seed host configure --tags dnf --kolla-tags none
```

### **Package Update**

To update one or more packages:

```
(kayobe) $ kayobe seed host package update --packages <package1>,<package2>
```

To update all eligible packages, use \*, escaping if necessary:

```
(kayobe) $ kayobe seed host package update --packages "*"
```

To only install updates that have been marked security related:

```
(kayobe) $ kayobe seed host package update --packages "*" --security
```

Note that these commands do not affect packages installed in containers, only those installed on the host.

Packages can also be updated on the seed hypervisor host, if one is in use:

```
(kayobe) \ kayobe seed hypervisor package update --packages <package1>, \rightarrow<package2>
```

## **Kernel Updates**

If the kernel has been updated, you will probably want to reboot the seed host to boot into the new kernel. This can be done using a command such as the following:

```
(kayobe) $ kayobe seed host command run --command "shutdown -r" --become
```

# **Examining the Bifrost Container**

The seed host runs various services required for a standalone Ironic deployment. These all run in a single bifrost\_deploy container.

It can often be helpful to execute a shell in the bifrost container for diagnosing operational issues:

```
$ docker exec -it bifrost_deploy bash
```

Services are run via Systemd:

```
(bifrost_deploy) systemctl
```

Logs are stored in /var/log/kolla/, which is mounted to the kolla\_logs Docker volume.

# **Accessing the Seed Services**

The Ironic and Ironic inspector APIs can be accessed via the baremetal command line interface:

```
(bifrost_deploy) $ export OS_CLOUD=bifrost
(bifrost_deploy) $ baremetal node list
(bifrost_deploy) $ baremetal introspection list
```

### **Backup & Restore**

There are two main approaches to backing up and restoring data on the seed. A backup may be taken of the Ironic databases. Alternatively, a Virtual Machine backup may be used if running the seed services in a VM. The former will consume less storage. Virtual Machine backups are not yet covered here, neither is scheduling of backups. Any backup and restore procedure should be tested in advance.

#### **Database Backup & Restore**

A backup may be taken of the database, using one of the many tools that exist for backing up MariaDB databases.

A simple approach that should work for the typically modestly sized seed database is mysqldump. The following commands should all be executed on the seed.

3.9. Administration 171

## **Backup**

It should be safe to keep services running during the backup, but for maximum safety they may optionally be stopped:

```
docker exec -it bifrost_deploy systemctl stop ironic ironic-inspector
```

Then, to perform the backup:

```
docker exec -it bifrost_deploy \
mysqldump --all-databases --single-transaction --routines --triggers > seed-
→backup.sql
```

If the services were stopped prior to the backup, start them again:

```
docker exec -it bifrost_deploy systemctl start ironic ironic-inspector
```

#### **Restore**

Prior to restoring the database, the Ironic and Ironic Inspector services should be stopped:

```
docker exec -it bifrost_deploy systemctl stop ironic ironic-inspector
```

The database may then safely be restored:

```
docker exec -i bifrost_deploy \
mysql < seed-backup.sql</pre>
```

Finally, start the Ironic and Ironic Inspector services again:

```
docker exec -it bifrost_deploy systemctl start ironic ironic-inspector
```

### **Running Commands**

It is possible to run a command on the seed host:

```
(kayobe) $ kayobe seed host command run --command "<command>"
```

For example:

```
(kayobe) $ kayobe seed host command run --command "service docker restart"
```

Commands can also be run on the seed hypervisor host, if one is in use:

```
(kayobe) $ kayobe seed hypervisor host command run --command "<command>"
```

To execute the command with root privileges, add the --become argument. Adding the --verbose argument allows the output of the command to be seen.

## 3.9.3 Infra VM Administration

## **Deprovisioning Infrastructure VMs**

#### Note

This step will destroy the infrastructure VMs and associated data volumes. Make sure you backup any data you want to keep.

To deprovision all VMs:

```
(kayobe) $ kayobe infra vm deprovision
```

This can be limited to a subset of the nodes using the --limit option:

(kayobe) \$ kayobe infra vm deprovision --limit example-vm-1

# **Updating Packages**

It is possible to update packages on the infrastructure VMs.

# **Package Repositories**

If using custom DNF package repositories on CentOS or Rocky, it may be necessary to update these prior to running a package update. To do this, update the configuration in \${KAYOBE\_CONFIG\_PATH}/dnf. yml and run the following command:

(kayobe) \$ kayobe infra vm host configure --tags dnf

## **Package Update**

To update one or more packages:

To update all eligible packages, use \*, escaping if necessary:

```
(kayobe) $ kayobe infra vm host package update --packages "*"
```

To only install updates that have been marked security related:

```
(kayobe) $ kayobe infra vm host package update --packages "*" --security
```

Note that these commands do not affect packages installed in containers, only those installed on the host.

3.9. Administration 173

## **Kernel Updates**

If the kernel has been updated, you will probably want to reboot the host to boot into the new kernel. This can be done using a command such as the following:

(kayobe) \$ kayobe infra vm host command run --command "shutdown -r" --become

# **Running Commands**

It is possible to run a command on the host:

```
(kayobe) $ kayobe infra vm host command run --command "<command>"
```

For example:

```
(kayobe) $ kayobe infra vm host command run --command "service docker restart"
```

Commands can also be run on the seed hypervisor host, if one is in use:

```
(kayobe) $ kayobe seed hypervisor host command run --command "<command>"
```

To execute the command with root privileges, add the --become argument. Adding the --verbose argument allows the output of the command to be seen.

### 3.9.4 Overcloud Administration

# **Updating Packages**

It is possible to update packages on the overcloud hosts.

## **Package Repositories**

If using custom DNF package repositories on CentOS or Rocky, it may be necessary to update these prior to running a package update. To do this, update the configuration in \${KAYOBE\_CONFIG\_PATH}/dnf.yml and run the following command:

```
(kayobe) $ kayobe overcloud host configure --tags dnf --kolla-tags none
```

### **Package Update**

To update one or more packages:

To update all eligible packages, use \*, escaping if necessary:

```
(kayobe) $ kayobe overcloud host package update --packages "*"
```

To only install updates that have been marked security related:

```
(kayobe) $ kayobe overcloud host package update --packages "*" --security
```

Note that these commands do not affect packages installed in containers, only those installed on the host.

## **Kernel Updates**

If the kernel has been updated, you will probably want to reboot the hosts to boot into the new kernel. This can be done using a command such as the following:

```
(kayobe) \$ kayobe overcloud host command run --command "shutdown -r" --become
```

It is normally best to apply this to control plane hosts in batches to avoid clustered services from losing quorum. This can be achieved using the --limit argument, and ensuring services are fully up after rebooting before proceeding with the next batch.

# **Running Commands**

It is possible to run a command on the overcloud hosts:

```
(kayobe) $ kayobe overcloud host command run --command "<command>"
```

For example:

```
(kayobe) \ kayobe overcloud host command run --command "service docker restart _{\rightarrow} "
```

To execute the command with root privileges, add the --become argument. Adding the --verbose argument allows the output of the command to be seen.

# **Reconfiguring Containerised Services**

When configuration is changed, it is necessary to apply these changes across the system in an automated manner. To reconfigure the overcloud, first make any changes required to the configuration on the Ansible control host. Next, run the following command:

```
(kayobe) $ kayobe overcloud service reconfigure
```

In case not all services configuration have been modified, performance can be improved by specifying Ansible tags to limit the tasks run in kayobe and/or kolla-ansibles playbooks. This may require knowledge of the inner workings of these tools but in general, kolla-ansible tags the play used to configure each service by the name of that service. For example: nova, neutron or ironic. Use -t or --tags to specify kayobe tags and -kt or --kolla-tags to specify kolla-ansible tags. For example:

```
(kayobe) $ kayobe overcloud service reconfigure --tags config --kolla-tags

→nova,ironic
```

3.9. Administration 175

## **Deploying Updated Container Images**

A common task is to deploy updated container images, without configuration changes. This might be to roll out an updated container OS or to pick up some package updates. This should be faster than a full deployment or reconfiguration.

To deploy updated container images:

```
(kayobe) $ kayobe overcloud service deploy containers
```

Note that if there are configuration changes, these will not be applied using this command so if in doubt, use a normal kayobe overcloud service deploy.

In case not all services containers have been modified, performance can be improved by specifying Ansible tags to limit the tasks run in kayobe and/or kolla-ansibles playbooks. This may require knowledge of the inner workings of these tools but in general, kolla-ansible tags the play used to configure each service by the name of that service. For example: nova, neutron or ironic. Use -t or --tags to specify kayobe tags and -kt or --kolla-tags to specify kolla-ansible tags. For example:

(kayobe) \$ kayobe overcloud service deploy containers --kolla-tags nova,ironic

# **Upgrading Containerised Services**

Containerised control plane services may be upgraded by replacing existing containers with new containers using updated images which have been pulled from a registry or built locally. If using an updated version of Kayobe or upgrading from one release of OpenStack to another, be sure to follow the *kayobe upgrade guide*. It may be necessary to upgrade one or more services within a release, for example to apply a patch or minor release.

To upgrade the containerised control plane services:

```
(kayobe) $ kayobe overcloud service upgrade
```

As for the reconfiguration command, it is possible to specify tags for Kayobe and/or kolla-ansible:

```
(kayobe) $ kayobe overcloud service upgrade --tags config --kolla-tags⊔
→keystone
```

## **Running Prechecks**

Sometimes it may be useful to run prechecks without deploying services:

```
(kayobe) $ kayobe overcloud service prechecks
```

As for other similar commands, it is possible to specify tags for Kayobe and/or kolla-ansible:

```
(kayobe) $ kayobe overcloud service upgrade --tags config --kolla-tags<sub>□</sub> ⇒keystone
```

# **Stopping the Overcloud Services**

### Note

This step will stop all containers on the overcloud hosts.

To stop the overcloud services:

(kayobe) \$ kayobe overcloud service stop --yes-i-really-really-mean-it

It should be noted that this state is persistent - containers will remain stopped after a reboot of the host on which they are running.

It is possible to limit the operation to particular hosts via --kolla-limit, or to particular services via --kolla-tags. It is also possible to avoid stopping the common containers via --kolla-skip-tags common. For example:

(kayobe) \$ kayobe overcloud service stop kolla-tags glance,nova kolla-skip-tags common

## **Destroying the Overcloud Services**

### Note

This step will destroy all containers, container images, volumes and data on the overcloud hosts.

To destroy the overcloud services:

(kayobe) \$ kayobe overcloud service destroy --yes-i-really-really-mean-it

## **Deprovisioning The Cloud**

## Note

This step will power down the overcloud hosts and delete their nodes instance state from the seeds ironic service. This command will print a list of hosts which will be deprovisioned, you must type yes to confirm. To automatically confirm, pass the arguments -e confirm\_deprovision=yes.

To deprovision the overcloud:

(kayobe) \$ kayobe overcloud deprovision

3.9. Administration 177

# **Saving Overcloud Service Configuration**

It is often useful to be able to save the configuration of the control plane services for inspection or comparison with another configuration set prior to a reconfiguration or upgrade. This command will gather and save the control plane configuration for all hosts to the Ansible control host:

```
(kayobe) $ kayobe overcloud service configuration save
```

The default location for the saved configuration is \$PWD/overcloud-config, but this can be changed via the output-dir argument. To gather configuration from a directory other than the default /etc/kolla, use the node-config-dir argument.

# **Generating Overcloud Service Configuration**

Prior to deploying, reconfiguring, or upgrading a control plane, it may be useful to generate the configuration that will be applied, without actually applying it to the running containers. The configuration should typically be generated in a directory other than the default configuration directory of /etc/kolla, to avoid overwriting the active configuration:

```
(kayobe) \ kayobe overcloud service configuration generate --node-config-dir / \rightarrowpath/to/generated/config
```

The configuration will be generated remotely on the overcloud hosts in the specified directory, with one subdirectory per container. This command may be followed by kayobe overcloud service configuration save to gather the generated configuration to the Ansible control host.

# **Validating Overcloud Service Configuration**

Issues can arise in Kolla Ansible deployments when incorrect options are used in configuration files. This is because OpenStack services will ignore unknown options. It is also important to keep on top of deprecated options that may be removed in the future. The oslo-config-validator can be used to check both of these. This command will run it on the OpenStack control plane services:

```
(kayobe) \ kayobe overcloud service configuration validate --output-dir /path/\ \rightarrowto/save/results
```

### **Performing Database Backups**

Database backups can be performed using the underlying support in Kolla Ansible.

In order to enable backups, enable Mariabackup in \${KAYOBE\_CONFIG\_PATH}/kolla.yml:

```
kolla_enable_mariabackup: true
```

To apply this change, use the *kayobe overcloud service reconfigure* command.

To perform a full backup, run the following command:

```
kayobe overcloud database backup
```

Or to perform an incremental backup, run the following command:

kayobe overcloud database backup --incremental

Further information on backing up and restoring the database is available in the Kolla Ansible documentation.

## **Performing Database Recovery**

Recover a completely stopped MariaDB cluster using the underlying support in Kolla Ansible.

To perform recovery run the following command:

kayobe overcloud database recover

Or to perform recovery on specified host, run the following command:

kayobe overcloud database recover --force-recovery-host <host>

By default the underlying kolla-ansible will automatically determine which host to use, and this option should not be used.

# **Gathering Facts**

The following command may be used to gather facts for all overcloud hosts, for both Kayobe and Kolla Ansible:

kayobe overcloud facts gather

This may be useful to populate a fact cache in advance of other operations.

# 3.9.5 Baremetal Compute Node Management

When enrolling new hardware or performing maintenance, it can be useful to be able to manage many bare metal compute nodes simultaneously.

In all cases, commands are delegated to one of the controller hosts, and executed concurrently. Note that ansibles forks configuration option, which defaults to 5, may limit the number of nodes configured concurrently.

By default these commands wait for the state transition to complete for each node. This behavior can be changed by overriding the variable baremetal\_compute\_wait via -e baremetal\_compute\_wait=False

3.9. Administration 179

# Register

This is an experimental workflow which acts as an alternative to enrolling nodes through inspection. Bare metal compute nodes can be registered in Ironic via Kayobe if defined in the Kayobe inventory. An example hosts file for group r1 is below:

```
[r1]
hv100 ipmi_address=1.2.3.4
...
[baremetal-compute:children]
r1
```

You should also define a group\_vars file for this group containing the Ironic variables, this could be in etc/kayobe/inventory/group\_vars/r1/ironic\_vars or in the environment you are using.

```
ironic_driver: redfish
ironic_driver_info
 redfish_system_id: "{{ ironic_redfish_system_id }}"
 redfish_address: "{{ ironic_redfish_address }}"
 redfish_username: "{{ ironic_redfish_username }}"
 redfish_password: "{{ ironic_redfish_password }}"
 redfish_verify_ca: "{{ ironic_redfish_verify_ca }}"
 ipmi_address: "{{ ipmi_address }}"
ironic_properties:
 capabilities: "{{ ironic_capabilities }}"
ironic_resource_class: "example_resource_class"
ironic_redfish_system_id: "/redfish/v1/Systems/System.Embedded.1"
ironic_redfish_verify_ca: "{{ inspector_rule_var_redfish_verify_ca }}"
ironic_redfish_address: "{{ ipmi_address }}"
ironic_redfish_username: "{{ inspector_redfish_username }}"
ironic_redfish_password: "{{ inspector_redfish_password }}"
ironic_capabilities: "boot_option:local,boot_mode:uefi"
```

It is essential that the Ironic username and password match the BMC username and password for your nodes. If the username and password combination is not the same for the entire group you will need to adjust your configuration accordingly. The IPMI address should also match the BMC address for your node.

Once this has been completed you can begin enrolling the Ironic nodes:

```
(kayobe) $ kayobe baremetal compute register
```

Inspector is not used to discover nodes and no node inspection will take place on enrollment, nodes will automatically be placed into manageable state. To inspect, you should use kayobe baremetal compute inspect following enrollment.

## Manage

A node may need to be set to the manageable provision state in order to perform certain management operations, or when an enrolled node is transitioned into service. In order to manage a node, it must be in one of these states: enroll, available, cleaning, clean failed, adopt failed or inspect failed. To move the baremetal compute nodes to the manageable provision state:

(kayobe) \$ kayobe baremetal compute manage

## **Provide**

In order for nodes to be scheduled by nova, they must be available. To move the baremetal compute nodes from the manageable state to the available provision state:

(kayobe) \$ kayobe baremetal compute provide

# Inspect

Nodes must be in one of the following states: manageable, inspect failed, or available. To trigger hardware inspection on the baremetal compute nodes:

(kayobe) \$ kayobe baremetal compute inspect

### **Saving Hardware Introspection Data**

Introspection data will be stored in the nginx service within the inspection\_store container. This data may be saved to the control host:

(kayobe) \$ kayobe baremetal compute introspection data save

- --output-dir may be used to specify the directory in which introspection data files will be saved.
- --output-format may be used to set the format of the files.

#### Rename

Once nodes have been discovered, it is helpful to associate them with a name to make them easier to work with. If you would like the nodes to be named according to their inventory host names, you can run the following command:

(kayobe) \$ kayobe baremetal compute rename

This command will use the ipmi\_address host variable from the inventory to map the inventory host name to the correct node.

3.9. Administration 181

## **Update Deployment Image**

When the overcloud deployment images have been rebuilt or there has been a change to one of the following variables:

- ipa\_kernel\_upstream\_url
- ipa\_ramdisk\_upstream\_url

either by changing the url, or if the image to which they point has been changed, you need to update the deploy\_ramdisk and deploy\_kernel properties on the Ironic nodes. To do this you can run:

```
(kayobe) $ kayobe baremetal compute update deployment image
```

You can optionally limit the nodes in which this affects by setting baremetal-compute-limit:

```
(kayobe) $ kayobe baremetal compute update deployment image --baremetal-\rightarrowcompute-limit sand-6-1
```

which should take the form of an ansible host pattern. This is matched against the Ironic node name.

### **Ironic Serial Console**

To access the baremetal nodes from within Horizon you need to enable the serial console. For this to work the you must set kolla\_enable\_nova\_serialconsole\_proxy to true in etc/kayobe/kolla.yml:

```
kolla_enable_nova_serialconsole_proxy: true
```

The console interface on the Ironic nodes is expected to be ipmitool-socat, you can check this with:

```
openstack baremetal node show <node_id> --fields console_interface
```

where <node id> should be the UUID or name of the Ironic node you want to check.

If you have set kolla\_ironic\_enabled\_console\_interfaces in etc/kayobe/ironic.yml, it should include ipmitool-socat in the list of enabled interfaces.

The playbook to enable the serial console currently only works if the Ironic node name matches the inventory hostname.

Once these requirements have been satisfied, you can run:

```
(kayobe) $ kayobe baremetal compute serial console enable
```

This will reserve a TCP port for each node to use for the serial console interface. The allocations are stored in \${KAYOBE\_CONFIG\_PATH}/console-allocation.yml. The current implementation uses a global pool, which is specified by ironic\_serial\_console\_tcp\_pool\_start and ironic\_serial\_console\_tcp\_pool\_end; these variables can set in etc/kayobe/ironic.yml.

To disable the serial console you can use:

```
(kayobe) $ kayobe baremetal compute serial console disable
```

The port allocated for each node is retained and must be manually removed from \${KAYOBE\_CONFIG\_PATH}/console-allocation.yml if you want it to be reused by another Ironic node with a different name.

You can optionally limit the nodes targeted by setting baremetal-compute-limit:

(kayobe) \$ kayobe baremetal compute serial console enable --baremetal-compute-→limit sand-6-1

which should take the form of an ansible host pattern.

### Serial console auto-enable

To enable the serial consoles automatically on kayobe overcloud post configure, you can set ironic\_serial\_console\_autoenable in etc/kayobe/ironic.yml:

ironic\_serial\_console\_autoenable: true

## 3.10 Resources

This section contains links to external Kayobe resources.

# 3.10.1 A Universe From Nothing

### Note

The A Universe From Nothing deployment guide is intended for educational & testing purposes only. It is *not* production ready.

Originally created as a workshop, A Universe From Nothing is an example guide for the deployment of Kayobe on virtual hardware. You can find it on GitHub here.

The repository contains a configuration suitable for deploying containerised OpenStack using Kolla, Ansible and Kayobe. The guide makes use of Tenks to provision a virtual baremetal environment running on a single hypervisor.

To complete the walkthrough you will require a baremetal or VM hypervisor running CentOS Stream 9, Rocky Linux 9 or Ubuntu Noble 24.04 (since Dalmatian 17.0.0) with at least 32GB RAM & 80GB disk space. Preparing the deployment can take some time - where possible it is beneficial to snapshot the hypervisor. We advise making a snapshot after creating the initial seed VM as this will make additional deployments significantly faster.

# 3.11 Advanced Documentation

### 3.11.1 Control Plane Service Placement

### Note

This is an advanced topic and should only be attempted when familiar with kayobe and OpenStack.

3.10. Resources 183

The default configuration in kayobe places all control plane services on a single set of servers described as controllers. In some cases it may be necessary to introduce more than one server role into the control plane, and control which services are placed onto the different server roles.

# Configuration

# **Overcloud Inventory Discovery**

If using a seed host to enable discovery of the control plane services, it is necessary to configure how the discovered hosts map into kayobe groups. This is done using the overcloud\_group\_hosts\_map variable, which maps names of kayobe groups to a list of the hosts to be added to that group.

This variable will be used during the command kayobe overcloud inventory discover. An inventory file will be generated in \${KAYOBE\_CONFIG\_PATH}/inventory/overcloud with discovered hosts added to appropriate kayobe groups based on overcloud\_group\_hosts\_map.

## **Kolla-ansible Inventory Mapping**

Once hosts have been discovered and enrolled into the kayobe inventory, they must be added to the kolla-ansible inventory. This is done by mapping from top level kayobe groups to top level kolla-ansible groups using the kolla\_overcloud\_inventory\_top\_level\_group\_map variable. This variable maps from kolla-ansible groups to lists of kayobe groups, and variables to define for those groups in the kolla-ansible inventory.

## **Variables For Custom Server Roles**

Certain variables must be defined for hosts in the overcloud group. For hosts in the controllers group, many variables are mapped to other variables with a controller\_prefix in files under ansible/inventory/group\_vars/controllers/. This is done in order that they may be set in a global extra variables file, typically controllers.yml, with defaults set in ansible/inventory/group\_vars/all/controllers. A similar scheme is used for hosts in the monitoring group.

 Variable
 Purpose

 ansible\_user
 Username with which to access the host via SSH.

 bootstrap\_user
 Username with which to access the host before ansible\_user is configured.

 lvm\_groups
 List of LVM volume groups to configure. See mrlesmithjr.manage\_lvm role for format.

 mdadm\_arrays
 List of software RAID arrays. See mrlesmithjr.mdadm role for format.

 network\_interface
 List of names of networks to which the host is connected.

 sysctl\_parameters
 Dict of sysctl parameters to set.

Table 3: Overcloud host variables

If configuring BIOS and RAID via kayobe overcloud bios raid configure, the following variables should also be defined:

List of users to create. See singleplatform-eng.users role

Table 4: Overcloud BIOS & RAID host variables

Variable	Purpose
bios_confi	Dict mapping BIOS configuration options to their required values. See stackhpc.drac
	role for format.
raid_confi	List of RAID virtual disks to configure. See stackhpc.drac role for format.

These variables can be defined in inventory host or group variables files, under \${KAYOBE\_CONFIG\_PATH}/inventory/host\_vars/<host> or \${KAYOBE\_CONFIG\_PATH}/inventory/group\_vars/<group> respectively.

### **Custom Kolla-ansible Inventories**

As an advanced option, it is possible to fully customise the content of the kolla-ansible inventory, at various levels. To facilitate this, kayobe breaks the kolla-ansible inventory into three separate sections.

**Top level** groups define the roles of hosts, e.g. controller or compute, and it is to these groups that hosts are mapped directly.

**Components** define groups of services, e.g. nova or ironic, which are mapped to top level groups.

**Services** define single containers, e.g. nova-compute or ironic-api, which are mapped to components.

The default top level inventory is generated from kolla\_overcloud\_inventory\_top\_level\_group\_map. Kayobes component- and service-level inventory for kolla-ansible is static, and taken from the kolla-ansible example multinode inventory. The complete inventory is generated by concatenating these inventories.

Each level may be separately overridden by setting the following variables:

Table 5: Custom kolla-ansible inventory variables

Variable	Purpose
kolla_overcloud_inventory_custom	Overcloud inventory containing a mapping from top level groups to hosts.
kolla_overcloud_inventory_custom	Overcloud inventory containing a mapping from components to top level groups.
kolla_overcloud_inventory_custom	Overcloud inventory containing a mapping from services to components.
kolla_overcloud_inventory_custom	Full overcloud inventory contents.

# **Examples**

# **Example 1: Adding Network Hosts**

This example walks through the configuration that could be applied to enable the use of separate hosts for neutron network services and load balancing. The control plane consists of three controllers, controller-[0-2], and two network hosts, network-[0-1]. All file paths are relative to \${KAYOBE\_CONFIG\_PATH}.

First, we must make the network group separate from controllers:

Listing 181: inventory/groups

```
[controllers]
# Empty group to provide declaration of controllers group.

[network]
# Empty group to provide declaration of network group.
```

Then, we must map the hosts to kayobe groups.

Listing 182: overcloud.yml

```
overcloud_group_hosts_map:
    controllers:
    - controller-0
    - controller-1
    - controller-2
    network:
    - network-0
    - network-1
```

Next, we must map these groups to kolla-ansible groups.

Listing 183: kolla.yml

```
kolla_overcloud_inventory_top_level_group_map:
    control:
        groups:
        - controllers
    network:
        groups:
        - network
```

Finally, we create a group variables file for hosts in the network group, providing the necessary variables for a control plane host.

Listing 184: inventory/group\_vars/network

```
ansible_user: "{{ kayobe_ansible_user }}"
bootstrap_user: "{{ controller_bootstrap_user }}"
lvm_groups: "{{ controller_lvm_groups }}"
mdadm_arrays: "{{ controller_mdadm_arrays }}"

(continues on next page)
```

(continued from previous page)

```
network_interfaces: "{{ controller_network_host_network_interfaces }}"
sysctl_parameters: "{{ controller_sysctl_parameters }}"
users: "{{ controller_users }}"
```

Here we are using the controller-specific values for some of these variables, but they could equally be different.

## **Example 2: Overriding the Kolla-ansible Inventory**

This example shows how to override one or more sections of the kolla-ansible inventory. All file paths are relative to \${KAYOBE\_CONFIG\_PATH}.

It is typically best to start with an inventory template taken from the Kayobe source code, and then customize it. The templates can be found in ansible/roles/kolla-ansible/templates, e.g. components template is overcloud-components.j2.

First, create a file containing the customised inventory section. Well use the **components** section in this example.

Listing 185: kolla/inventory/overcloud-components.j2

```
[nova]
control

[ironic]
{% if kolla_enable_ironic | bool %}
control
{% endif %}
...
```

Next, we must configure kayobe to use this inventory template.

Listing 186: kolla.yml

Here we use the template lookup plugin to render the Jinja2-formatted inventory template.

## Fine-grained placement

Kayobe has fairly coarse-grained default groups - controller, compute, etc, which work well in the majority of cases. Kolla Ansible allows much more fine-grained placement on a per-service basis, e.g. ironic-conductor. If the operator has taken advantage of this fine-grained placement, then it is possible that some of the assumptions in Kayobe may be incorrect. This is one downside of the split between Kayobe and Kolla Ansible.

For example, Ironic conductor services may have been moved to a subset of the top level controllers group. In this case, we would not want the Ironic networks to be mapped to all hosts in the controllers group - only those running Ironic conductor services. The same argument can be made if the loadbalancer

services (HAProxy & keepalived) or Neutron dataplane services (e.g. L3 & DHCP agents) have been separated from the top level network group.

In these cases, the following variables may be used to tune placement:

## controller\_ironic\_conductor\_group

Ansible inventory group in which Ironic conductor services are deployed. Default is controllers.

## controller\_ironic\_inspector\_group

Ansible inventory group in which Ironic inspector services are deployed. Default is controllers.

# controller\_loadbalancer\_group

Ansible inventory group in which control plane load balancer services are deployed. Default is network.

## controller\_network\_group

Ansible inventory group in which network data plane services are deployed. Default is network.

# 3.11.2 Custom Ansible Playbooks

Kayobe supports running custom Ansible playbooks located outside of the kayobe project. This provides a flexible mechanism for customising a control plane. Access to the kayobe variables is possible, ensuring configuration does not need to be repeated.

# **Kayobe Custom Playbook API**

Explicitly allowing users to run custom playbooks with access to the kayobe variables elevates the variable namespace and inventory to become an interface. This raises questions about the stability of this interface, and the guarantees it provides.

The following guidelines apply to the custom playbook API:

- Only variables defined in the kayobe configuration files under etc/kayobe are supported.
- The groups defined in etc/kayobe/inventory/groups are supported.
- Any change to a supported variable (rename, schema change, default value change, or removal) or supported group (rename or removal) will follow a deprecation period of one release cycle.
- Kayobes internal roles may not be used.

Note that these are guidelines, and exceptions may be made where appropriate.

# **Running Custom Ansible Playbooks**

Run one or more custom ansible playbooks:

```
(kayobe) $ kayobe playbook run <playbook>[ <playbook>...]
```

Playbooks do not by default have access to the Kayobe playbook group variables, filter plugins, and test plugins, since these are relative to the current playbooks directory. This can be worked around by creating symbolic links to the Kayobe repository from the Kayobe configuration.

# **Packaging Custom Playbooks With Configuration**

The kayobe project encourages its users to manage configuration for a cloud using version control, based on the kayobe-config repository. Storing custom Ansible playbooks in this repository makes a lot of sense, and kayobe has special support for this.

It is recommended to store custom playbooks in \$KAYOBE\_CONFIG\_PATH/ansible/. It is also possible to use the following subdirectories, and since the Zed 13.0.0 release these will be available to all Kayobe playbook executions.

- roles
- collections
- action\_plugins
- filter\_plugins
- test\_plugins

Note that since the Zed 13.0.0 release, it is no longer necessary to create symlinks in order to use Kayobes roles, collections or plugins. Existing symlinks may be removed.

## **Ansible Galaxy**

Ansible Galaxy provides a means for sharing Ansible roles and collections. Kayobe configuration may provide a Galaxy requirements file that defines roles and collections to be installed from Galaxy. These roles and collections may then be used by custom playbooks.

Galaxy dependencies may be defined in \$KAYOBE\_CONFIG\_PATH/ansible/requirements.yml. These roles and collections will be installed in \$KAYOBE\_CONFIG\_PATH/ansible/roles/ and \$KAYOBE\_CONFIG\_PATH/ansible/collections when bootstrapping the Ansible control host:

```
(kayobe) $ kayobe control host bootstrap
```

And updated when upgrading the Ansible control host:

```
(kayobe) $ kayobe control host upgrade
```

### **Example: roles**

The following example adds a foo.yml playbook to a set of kayobe configuration. The playbook uses a Galaxy role, bar.baz.

Here is the kayobe configuration repository structure:

```
etc/kayobe/
ansible/
foo.yml
requirements.yml
roles/
bifrost.yml
```

Here is the playbook, ansible/foo.yml:

```
---
- hosts: controllers
roles:
- name: bar.baz
```

Here is the Galaxy requirements file, ansible/requirements.yml:

```
roles:
- bar.baz
```

We should first install the Galaxy role dependencies, to download the bar.baz role:

```
(kayobe) $ kayobe control host bootstrap
```

Then, to run the foo.yml playbook:

```
(kayobe) $ kayobe playbook run $KAYOBE_CONFIG_PATH/ansible/foo.yml
```

## **Example: collections**

The following example adds a foo.yml playbook to a set of kayobe configuration. The playbook uses a role from a Galaxy collection, bar.baz.qux.

Here is the kayobe configuration repository structure:

```
etc/kayobe/
ansible/
collections/
foo.yml
requirements.yml
bifrost.yml
...
```

Here is the playbook, ansible/foo.yml:

```
---
- hosts: controllers
roles:
- name: bar.baz.qux
```

Here is the Galaxy requirements file, ansible/requirements.yml:

```
collections:
- bar.baz
```

We should first install the Galaxy dependencies, to download the bar.baz collection:

```
(kayobe) $ kayobe control host bootstrap
```

Then, to run the foo.yml playbook:

```
(kayobe) $ kayobe playbook run $KAYOBE_CONFIG_PATH/ansible/foo.yml
```

### Hooks

# Warning

Hooks are an experimental feature and the design could change in the future. You may have to update your config if there are any changes to the design. This warning will be removed when the design has been stabilised.

Hooks allow you to automatically execute custom playbooks at certain points during the execution of a kayobe command. The point at which a hook is run is referred to as a target. Please see the *list of available targets*.

Hooks are created by symlinking an existing playbook into the relevant directory under \$KAYOBE\_CONFIG\_PATH/hooks. Kayobe will search the hooks directory for sub-directories matching <command>.<target>.d, where command is the name of a kayobe command with any spaces replaced with dashes, and target is one of the supported targets for the command.

For example, when using the command:

```
(kayobe) $ kayobe control host bootstrap
```

kayobe will search the paths:

- \$KAYOBE\_CONFIG\_PATH/hooks/control-host-bootstrap/pre.d
- \$KAYOBE\_CONFIG\_PATH/hooks/control-host-bootstrap/post.d

Any playbooks listed under the pre.d directory will be run before kayobe executes its own playbooks and any playbooks under post.d will be run after. You can affect the order of the playbooks by prefixing the symlink with a sequence number. The sequence number must be separated from the hook name with a dash. Playbooks with smaller sequence numbers are run before playbooks with larger ones. Any ties are broken by alphabetical ordering.

For example to run the playbook foo.yml after kayobe overcloud host configure, you could do the following:

```
(kayobe) $ mkdir -p ${KAYOBE_CONFIG_PATH}/hooks/overcloud-host-configure/post.

d
(kayobe) $ cd ${KAYOBE_CONFIG_PATH}/hooks/overcloud-host-configure/post.d
(kayobe) $ ln -s ../../ansible/foo.yml 10-foo.yml
```

The sequence number for the foo.yml playbook is 10.

Hook execution can be disabled with --skip-hooks. --skip-hooks all will halt hook execution altogether. --skip-hooks <pattern> will skip playbooks matching the <pattern>.

For example, if the following playbooks exist:

- \$KAYOBE\_CONFIG\_PATH/hooks/control-host-bootstrap/pre.d/example1.yml
- \$KAYOBE\_CONFIG\_PATH/hooks/control-host-bootstrap/pre.d/example2.yml
- \$KAYOBE\_CONFIG\_PATH/hooks/control-host-bootstrap/post.d/example1.yml

And the following command is used:

```
(kayobe) $ kayobe control host bootstrap --skip-hooks example1
```

Only \$KAYOBE\_CONFIG\_PATH/hooks/control-host-bootstrap/pre.d/example2.yml will be executed.

This example assumes that the term example1 does not appear in \$KAYOBE\_CONFIG\_PATH. If it did, all hooks would be skipped.

## Failure handling

If the exit status of any playbook, including built-in playbooks and custom hooks, is non-zero, kayobe will not run any subsequent hooks or built-in kayobe playbooks. Ansible provides several methods for preventing a task from producing a failure. Please see the Ansible documentation for more details. Below is an example showing how you can use the <code>ignore\_errors</code> option to prevent a task from causing the playbook to report a failure:

```
---
- name: Failure example
hosts: localhost
tasks:
- name: Deliberately fail
fail:
ignore_errors: true
```

A failure in the Deliberately fail task would not prevent subsequent tasks, hooks, and playbooks from running.

# **Targets**

The following targets are available for all commands:

Table 6: all commands

T Description

g

- p. Runs before a kayobe command has start executing
- p Runs after a kayobe command has finished executing

# 3.11.3 Multiple Environments

## Warning

Support for multiple Kayobe environments is considered experimental: its design may change in future versions without a deprecation period.

Sometimes it can be useful to support deployment of multiple environments from a single Kayobe configuration. Most commonly this is to support a deployment pipeline, such as the traditional development, test, staging and production combination. Since the Wallaby release, it is possible to include multiple environments within a single Kayobe configuration, each providing its own Ansible inventory and variables. This section describes how to use multiple environments with Kayobe.

## **Defining Kayobe Environments**

By default, a Kayobe configuration directory contains a single environment, represented by the Ansible inventory located at \$KAYOBE\_CONFIG\_PATH/inventory, extra variables files (\$KAYOBE\_CONFIG\_PATH/\*.yml), custom Ansible playbooks and hooks, and Kolla configuration.

Supporting multiple environments is done through a \$KAYOBE\_CONFIG\_PATH/environments directory, under which each directory represents a different environment. Each environment contains its own Ansible inventory, extra variable files, hooks, and Kolla configuration. The following layout shows two environments called staging and production within a single Kayobe configuration.

```
$KAYOBE_CONFIG_PATH/
environments/
ăă production/
ăă ăă hooks/
ăă ăă aă overcloud-service-deploy/
ăă ăă ăă
         ăă pre.d/
ăă ăă ăă ăă
                 1-prep-stuff.yml
ăă ăă
       inventory/
ăă ăă ăă groups
ăă ăă ăă group_vars/
ăă ăă ăă hosts
ăă ăă ăă host_vars/
ăă ăă overcloud
ăă ăă kolla/
ăă ăă ăă config/
ăă ăă globals.yml
ăă ăă passwords.yml
ăă ăă network-allocation.yml
ăă ăă networks.yml
ăă ăă overcloud.yml
ăă
   staging/
ăă
        inventory/
ăă
       ăă groups
ăă
       ăă group_vars/
       ăă hosts
ăă
```

(continues on next page)

(continued from previous page)

```
ăă
       ăă host_vars/
ăă
       ăă overcloud
        kolla/
ăă
ăă
       ăă config/
       ăă globals.yml
ăă
ăă
       ăă passwords.yml
        network-allocation.yml
ăă
ăă
        networks.yml
        overcloud.yml
ăă
```

# **Naming**

The environment name kayobe is reserved for internal use. The name should be a valid directory name, otherwise there are no other restrictions.

### **Ansible Inventories**

Each environment can include its own inventory, which overrides any variable declaration done in the shared inventory. Typically, a shared inventory may be used to define groups and group variables, while hosts and host variables would be set in environment inventories. The following layout (ignoring non-inventory files) shows an example of multiple inventories.

```
$KAYOBE_CONFIG_PATH/
environments/
ăă production/
ăă ăă inventory/
ăă ăă ăă hosts
ăă ăă ăă host_vars/
ăă ăă overcloud
ăă staging/
ăă
       inventory/
ăă
      ăă hosts
      ăă host_vars/
ăă
ăă
      ăă overcloud
inventory/
    groups
     group_vars/
```

### **Custom Kolla Ansible inventories**

Kayobe has a *feature* to pass through additional inventories to Kolla Ansible. When using multiple environments, these are passed though as additional inventories to Ansible. The ordering is such that the inventory in the base layer of kayobe config overrides the internal kayobe inventory, and inventory in the environment overrides inventory in the base layer:

```
ansible-playbook -i <internal kayobe inventory> -i <inventory from base layer> \rightarrow -i <inventory from environment>
```

See Custom Kolla Inventory for more details.

### **Shared Extra Variables Files**

All of the extra variables files in the Kayobe configuration directory (\$KAYOBE\_CONFIG\_PATH/\*.yml) are shared between all environments. Each environment can override these extra variables through environment-specific extra variables files (\$KAYOBE\_CONFIG\_PATH/environments/<environment>/\*.yml).

This means that all configuration in shared extra variable files must apply to all environments. Where configuration differs between environments, move the configuration to extra variables files under each environment.

For example, to add environment-specific DNS configuration for variables in dns.yml, set these variables in \$KAYOBE\_CONFIG\_PATH/environments/<environment>/dns.yml:

```
$KAYOBE_CONFIG_PATH/
dns.yml
environments/
ăă production/
ăă ăă dns.yml
äă staging/
ăă ăă dns.yml
```

## **Network Configuration**

Networking is an area in which configuration is typically specific to an environment. There are two main global configuration files that need to be considered: networks.yml and network-allocation.yml.

Move the environment-specific parts of this configuration to environment-specific extra variables files:

- networks.yml -> \$KAYOBE\_CONFIG\_PATH/environments/<environment>/networks.yml
- network-allocation.yml -> \$KAYOBE\_CONFIG\_PATH/environments/<environment>/ network-allocation.yml

Other network configuration that may differ between environments includes:

- DNS (dns.yml)
- network interface names, which may be set via group variables in environment inventories

## **Other Configuration**

Typically it is necessary to customise overcloud\_group\_hosts\_map in each environment. This is done via the overcloud.yml file documented in *Control Plane Service Placement*.

When using baremetal compute nodes, allocation of TCP ports for serial console functionality is typically specific to an environment (console-allocation.yml). This file is automatically managed by Kayobe, like the network-allocation.yml file.

# **Kolla Configuration**

In the Wallaby release, Kolla configuration was independent in each environment. The Xena release supported combining environment-specific and shared configuration file content for the following subset of the files:

- kolla/config/bifrost/bifrost.yml
- kolla/config/bifrost/dib.yml
- kolla/config/bifrost/servers.yml
- kolla/globals.yml
- kolla/kolla-build.conf
- kolla/repos.yml or kolla/repos.yaml

The Antelope release expands upon this list to add support for combining Kolla Ansible custom service configuration. This behaviour is configured using two variables:

- kolla\_openstack\_custom\_config\_include\_globs: Specifies which files are considered when templating the Kolla configuration. The Kayobe defaults are set using kolla\_openstack\_custom\_config\_include\_globs\_default. An optional list of additional globs can be set using: kolla\_openstack\_custom\_config\_include\_globs\_extra. These are combined with kolla\_openstack\_custom\_config\_include\_globs\_default to produce kolla\_openstack\_custom\_config\_include\_globs. Each list entry is a dictionary with the following keys:
  - enabled: Boolean which determines if this rule is used. Set to false to disable the rule.
  - glob: String glob matching a relative path in the kolla/config directory

An example of such a rule:

```
enabled: '{{ kolla_enable_aodh | bool }}'
glob: aodh/**
```

- kolla\_openstack\_custom\_config\_rules: List of rules that specify the strategy to use when generating a particular file. The Kayobe defaults are set using kolla\_openstack\_custom\_config\_rules\_default. An optional list of additional rules can be set using: kolla\_openstack\_custom\_config\_rules\_extra. These are combined with kolla\_openstack\_custom\_config\_rules\_default to produce kolla\_openstack\_custom\_config\_rules. Each list entry is a dictionary with the format:
  - glob: A glob matching files for this rule to match on (relative to the search path)

- priority: The rules are processed in increasing priority order with the first rule matching taking effect
- strategy: How to process the matched file. One of copy, concat, template, merge\_configs, merge\_yaml
- params: Optional list of additional params to pass to module enacting the strategy

An example of such a rule:

```
glob: a/path/test.yml
strategy: merge_yaml
priority: 1000
params:
    extend_lists: true
```

The Kayobe defaults fallback to using the template strategy, with a priority of 65535. To override this behaviour configure a rule with a lower priority e.g:

```
glob: horizon/themes/**
strategy: copy
priority: 1000
```

The default INI merging strategy can be configured using: kolla\_openstack\_custom\_config\_ini\_merge\_strategy It defaults to concat for backwards compatibility. An alternative strategy is merge\_configs which will merge the two INI files so that values set in the environment take precedence over values set in the shared files. The caveat with the merge\_configs strategy is that files must template to valid INI. This is mostly an issue when you use raw Jinja tags, for example:

```
[defaults]
{% raw %}
{% if inventory_hostname in 'compute' %}
foo=bar
{% else %}
foo=baz
{% endif %}
{% endraw %}
```

After the first round of templating by Kayobe the raw tags are stripped. This leaves:

```
[defaults]
{% if inventory_hostname in 'compute' %}
foo=bar
{% else %}
foo=baz
{% endif %}
```

Which isnt valid INI (due to the Jinja if blocks) and cannot be merged. In most cases the templating can be refactored:

```
[defaults]
{% raw %}
foo={{ 'bar' if inventory_hostname in 'compute' else 'baz' }}
{% endraw %}
```

Alternatively, you can use Kolla host or group variables.

# Disabling the default rules

There are some convenience variables to disable a subset of the rules in kolla\_openstack\_custom\_config\_rules\_default:

• kolla\_openstack\_custom\_config\_rules\_default\_remove: Allows you remove a rule by matching on the glob:

```
kolla_openstack_custom_config_rules_default_remove:
- "**/*.ini"
```

- kolla\_openstack\_custom\_config\_merge\_configs\_enabled: Enables rules for matching INI files. Default is true.
- kolla\_openstack\_custom\_config\_merge\_yaml\_enabled: Enables rules for matching YAML files. Default is true.

These allow you to more easily keep in sync with the upstream defaults. If you had an override on kolla\_openstack\_custom\_config\_rules, that replicated most of kolla\_openstack\_custom\_config\_rules\_default youd have to keep this in sync with the upstream kayobe defaults.

# Search paths

When merging config files the following locations are searched to find files with an identical relative path:

- <environment-path>/kolla/config
- <shared-files-path>/kolla/config
- <kolla-openstack-role-path>/templates/kolla/config

Not all strategies use all of the files when generating the kolla config. For instance, the copy strategy will use the first file found when searching each of the paths.

There is a feature flag: kolla\_openstack\_custom\_config\_environment\_merging\_enabled, that may be set to false to prevent Kayobe searching the shared files path when merging configs. This is to replicate the legacy behaviour where the environment Kolla custom service configuration was not merged with the base layer. We still merge the files with Kayobes defaults in the kolla-openstack roles internal templates.

## **Managing Independent Environment Files**

For files that are independent in each environment, i.e. they do not support combining the environmentspecific and shared configuration file content, there are some techniques that may be used to avoid duplication.

For example, symbolic links can be used to share common variable definitions. It is advised to avoid sharing credentials between environments by making each Kolla passwords.yml file unique.

# **Custom Ansible Playbooks**

*Custom Ansible playbooks*, roles and requirements file under \$KAYOBE\_CONFIG\_PATH/ansible are currently shared across all environments.

### Hooks

Prior to the Caracal 16.0.0 release, *hooks* were shared across all environments. Since Caracal it is possible to define hooks on a per-environment basis. Hooks are collected from all environments and the base configuration. Where multiple hooks exist with the same name, the environments hook takes precedence and *replaces* the other hooks. Execution order follows the normal rules, regardless of where each hook is defined.

For example, the base configuration defines the following hooks:

- \$KAYOBE\_CONFIG\_PATH/hooks/overcloud-service-deploy/pre.d/1-base.yml
- \$KAYOBE\_CONFIG\_PATH/hooks/overcloud-service-deploy/pre.d/2-both.yml

The environment defines the following hooks:

- \$KAYOBE\_CONFIG\_PATH/environments/env/hooks/overcloud-service-deploy/pre.d/ 2-both.yml
- \$KAYOBE\_CONFIG\_PATH/environments/env/hooks/overcloud-service-deploy/pre.d/ 3-env.yml

The following hooks will execute in the order shown:

- \$KAYOBE\_CONFIG\_PATH/hooks/overcloud-service-deploy/pre.d/1-base.yml
- \$KAYOBE\_CONFIG\_PATH/environments/env/hooks/overcloud-service-deploy/pre.d/ 2-both.yml
- \$KAYOBE\_CONFIG\_PATH/environments/env/hooks/overcloud-service-deploy/pre.d/ 3-env.yml

# **Ansible Configuration**

Ansible configuration at \$KAYOBE\_CONFIG\_PATH/ansible.cfg or \$KAYOBE\_CONFIG\_PATH/kolla/ansible.cfg is currently shared across all environments.

# **Dynamic Variable Definitions**

It may be beneficial to define variables in a file shared by multiple environments, but still set variables to different values based on the environment. The Kayobe environment in use can be retrieved within Ansible via the kayobe\_environment variable. For example, some variables from \$KAYOBE\_CONFIG\_PATH/networks.yml could be shared in the following way:

```
Listing 187: $KAYOBE_CONFIG_PATH/networks.yml
```

```
external_net_fqdn: "{{ kayobe_environment }}-api.example.com"
```

This would configure the external FQDN for the staging environment at staging-api.example.com, while the production external FQDN would be at production-api.example.com.

# **Environment Dependencies**

## Warning

This is an experimental feature and is still subject to change whilst the design is finalised.

Since the Antelope 14.0.0 release, multiple environments can be layered on top of each of each other by declaring dependencies in a .kayobe-environment file located in the environment subdirectory. For example:

```
Listing 188: $KAYOBE_CONFIG_PATH/environments/environment-C/.kayobe-environment
```

```
dependencies:
```

- environment-B

Listing 189: \$KAYOBE\_CONFIG\_PATH/environments/environment-B/.kayobe-environment

```
dependencies:
```

- environment-A

Kayobe uses a dependency resolver to order these environments into a linear chain. Any dependency cycles in will result in an error. Using the example above the chain would be resolved to:

```
C -> B -> A
```

Where C is the environment with highest precedence. Kayobe will make sure to include the inventory and extra-vars in an order matching this chain when running any playbooks.

#### Mixin environments

Environment dependencies can be used to design fragments of re-useable configuration that can be shared across multiple environments. For example:

Listing 190: \$KAYOBE\_CONFIG\_PATH/environments/environment-A/.kayobe-environment

```
dependencies:
    - environment-mixin-1
    - environment-mixin-2
    - environment-mixin-3
```

In this case, each environment dependency could provide the configuration necessary for one or more features. The mixin environments do not necessarily need to define any dependencies between them, however Kayobe will perform a topological sort to determine a suitable precedence. Care should be taken to make sure that environments without an explicit ordering do not modify the same variables.

### **Final Considerations**

While its clearly desirable to keep staging functionally as close to production, this is not always possible due to resource constraints and other factors. Test and development environments can deviate further, perhaps only providing a subset of the functionality available in production, in a substantially different environment. In these cases it will clearly be necessary to use environment-specific configuration in a number of files. We cant cover all the cases here, but hopefully weve provided a set of techniques that can be used.

## **Using Kayobe Environments**

Once environments are defined, Kayobe can be instructed to manage them with the \$KAYOBE\_ENVIRONMENT environment variable or the --environment command-line argument:

```
(kayobe) $ kayobe control host bootstrap --environment staging
```

```
(kayobe) $ export KAYOBE_ENVIRONMENT=staging
(kayobe) $ kayobe control host bootstrap
```

The kayobe-env environment file in kayobe-config can also take an --environment argument, which exports the KAYOBE\_ENVIRONMENT environment variable.

```
(kayobe) $ source kayobe-env --environment staging
(kayobe) $ kayobe control host bootstrap
```

Finally, an environment name can be specified under \$KAYOBE\_CONFIG\_ROOT/.environment, which will be used by the kayobe-env script if no --environment argument is used. This is particularly useful when using a separate branch for each environment.

```
(kayobe) $ echo "staging" > .environment
(kayobe) $ source kayobe-env
(kayobe) $ kayobe control host bootstrap
```

# Warning

The locations of the Kolla Ansible source code and Python virtual environment remain the same for all environments when using the kayobe-env file. When using the same control host to manage multiple environments with different versions of Kolla Ansible, clone the Kayobe configuration in different locations, so that Kolla Ansible source repositories and Python virtual environments will not conflict with each other. The generated Kolla Ansible configuration is also shared: Kayobe will store the name of the active environment under \$KOLLA\_CONFIG\_PATH/.environment and produce a warning if a conflict is detected.

# Migrating to Kayobe Environments

Kayobe users already managing multiple environments will already have multiple Kayobe configurations, whether in separate repositories or in different branches of the same repository. Kayobe provides the kayobe environment create command to help migrating to a common repository and branch with multiple environments. For example, the following commands will create two new environments for production and staging based on existing Kayobe configurations.

This command recursively copies files and directories (except the environments directory if one exists) under the existing configuration to a new environment. Merging shared configuration must be done manually.

## 3.12 Contributor Guide

## 3.12.1 Contributor Guide

This guide is for contributors of the Kayobe project. It includes information on proposing your first patch and how to participate in the community. It also covers responsibilities of core reviewers and the Project Team Lead (PTL), and information about development processes.

We welcome everyone to join our project!

#### So You Want to Contribute

For general information on contributing to OpenStack, please check out the contributor guide to get started. It covers all the basics that are common to all OpenStack projects: the accounts you need, the basics of interacting with our Gerrit review system, how we communicate as a community, etc.

Below will cover the more project specific information you need to get started with Kayobe.

### **Basics**

The source repository for this project can be found at:

https://opendev.org/openstack/kayobe

### Communication

Kayobe shares communication channels with Kolla.

### **IRC Channel**

#openstack-kolla (channel logs) on OFTC

## **Weekly Meetings**

On Wednesdays in the IRC channel (meeting information)

## Mailing list (prefix subjects with [kolla])

http://lists.openstack.org/pipermail/openstack-discuss/

## **Meeting Agenda**

https://wiki.openstack.org/wiki/Meetings/Kolla

# Whiteboard (etherpad)

Keeping track of CI gate status, release status, stable backports, planning and feature development status. https://etherpad.openstack.org/p/KollaWhiteBoard

# **Contacting the Core Team**

The list in alphabetical order (on first name):

Name	IRC nick	Email address
Doug Szumski	dougsz	doug@stackhpc.com
John Garbutt	johnthetubaguy	john@johngarbutt.com
Kevin Tibi	ktibi	kevintibi@hotmail.com
Mark Goddard	mgoddard	mark@stackhpc.com
Pierre Riteau	priteau	pierre@stackhpc.com
Will Szumski	jovial	will@stackhpc.com

The current effective list is also available from Gerrit: https://review.opendev.org/#/admin/groups/1875, members

# **New Feature Planning**

New features are discussed via IRC or mailing list (with [kolla] prefix). Kayobe project keeps RFEs in Launchpad. Please use [RFE] prefix in the bug subject. Note this is the same place as for bugs. Specs are welcome but not strictly required.

## **Task Tracking**

Kayobe project tracks tasks in Launchpad. Note this is the same place as for bugs.

A more lightweight task tracking is done via etherpad - Whiteboard.

To see an overview of in-progress patches, sorted into useful sections, you can view the Kayobe Review Dashboard.

## Reporting a Bug

You found an issue and want to make sure we are aware of it? You can do so on Launchpad. Note this is the same place as for tasks.

# **Getting Your Patch Merged**

Most changes proposed to Kayobe require two +2 votes from core reviewers before +W. A release note is required on most changes as well. Release notes policy is described in *its own section*.

Significant changes should have documentation and testing provided with them.

# **Project Team Lead Duties**

All common PTL duties are enumerated in the PTL guide. Release tasks are described in the *Kayobe releases guide*.

## **Development**

### **Source Code Orientation**

There are a number of layers to Kayobe, so here we provide a few pointers to the major parts.

#### CLI

The Command Line Interface (CLI) is built using the cliff library. Commands are exposed as Python entry points in setup.cfg. These entry points map to classes in kayobe/cli/commands.py. The helper modules kayobe/ansible.py and kayobe/kolla\_ansible.py are used to execute Kayobe playbooks and Kolla Ansible commands respectively.

#### **Ansible**

Kayobes Ansible playbooks live in ansible/\*.yml, and these typically execute roles in ansible/roles/. Global variable defaults are defined in group variable files in ansible/inventory/group\_vars/all/ and these typically map to commented out variables in the configuration files in etc/kayobe/\*.yml. A number of custom Jinja filters exist in ansible/filter\_plugins/\*.py. Kayobe depends on roles and collections hosted on Ansible Galaxy, and these and their version requirements are defined in requirements.yml.

## **Ansible Galaxy**

Kayobe uses a number of Ansible roles and collections hosted on Ansible Galaxy. The role dependencies are tracked in requirements.yml, and specify required versions. The process for changing a Galaxy role or collection is as follows:

- 1. If required, develop changes for the role or collection. This may be done outside of Kayobe, or by modifying the code in place during development. If upstream changes to the code have already been made, this step can be skipped.
- 2. Commit changes to the role or collection, typically via a Github pull request.
- 3. Request that a tagged release of the role or collection be made, or make one if you have the necessary privileges.
- 4. Ensure that automatic imports are configured for the repository using e.g. a webhook notification, or perform a manual import of the role on Ansible Galaxy.
- 5. Modify the version in requirements.yml to match the new release of the role or collection.

# **Vagrant**

Kayobe provides a Vagrantfile that can be used to bring up a virtual machine for use as a development environment. The VM is based on the centos/8 CentOS 8 image, and supports the following providers:

- VirtualBox
- VMWare Fusion

The VM is configured with 4GB RAM and a 20GB HDD. It has a single private network in addition to the standard Vagrant NAT network.

## **Preparation**

First, ensure that Vagrant is installed and correctly configured to use the required provider. Also install the following vagrant plugins:

vagrant plugin install vagrant-reload vagrant-disksize

If using the VirtualBox provider, install the following vagrant plugin:

vagrant plugin install vagrant-vbguest

Note: if using Ubuntu 16.04 LTS, you may be unable to install any plugins. To work around this install the upstream version from www.virtualbox.org.

# **Usage**

Later sections in the development guide cover in more detail how to use the development VM in different configurations. These steps cover bringing up and accessing the VM.

Clone the kayobe repository:

git clone https://opendev.org/openstack/kayobe.git -b stable/2024.2

Change the current directory to the kayobe repository:

cd kayobe

Inspect kayobes Vagrantfile, noting the provisioning steps:

less Vagrantfile

Bring up a virtual machine:

vagrant up

Wait for the VM to boot, then SSH in:

vagrant ssh

# **Manual Setup**

This section provides a set of manual steps to set up a development environment for an OpenStack controller in a virtual machine using Vagrant and Kayobe.

For a more automated and flexible procedure, see Automated Setup.

# **Preparation**

Follow the steps in *Vagrant* to prepare your environment for use with Vagrant and bring up a Vagrant VM.

### **Manual Installation**

Sometimes the best way to learn a tool is to ditch the scripts and perform a manual installation.

SSH into the controller VM:

vagrant ssh

Source the kayobe virtualenv activation script:

source kayobe-venv/bin/activate

Change the current directory to the Vagrant shared directory:

cd /vagrant

Source the kayobe environment file:

source kayobe-env

Bootstrap the kayobe Ansible control host:

kayobe control host bootstrap

Configure the controller host:

kayobe overcloud host configure

At this point, container images must be acquired. They can either be built locally or pulled from an image repository if appropriate images are available.

Either build container images:

kayobe overcloud container image build

Or pull container images:

kayobe overcloud container image pull

Deploy the control plane services:

kayobe overcloud service deploy

Source the OpenStack environment file:

source \${KOLLA\_CONFIG\_PATH:-/etc/kolla}/admin-openrc.sh

Perform post-deployment configuration:

kayobe overcloud post configure

## **Next Steps**

The OpenStack control plane should now be active. Try out the following:

- register a user
- · create an image
- upload an SSH keypair
- · access the horizon dashboard

The cloud is your oyster!

#### To Do

Create virtual baremetal nodes to be managed by the OpenStack control plane.

# **Automated Setup**

This section provides information on the development tools provided by Kayobe to automate the deployment of various development environments.

For a manual procedure, see Manual Setup.

### **Overview**

The Kayobe development environment automation tooling is built using simple shell scripts. Some minimal configuration can be applied by setting the environment variables in dev/config.sh. Control plane configuration is typically provided via the kayobe-config-dev repository, although it is also possible to use your own Kayobe configuration. This allows us to build a development environment that is as close to production as possible.

#### **Environments**

The following development environments are supported:

- Overcloud (single OpenStack controller)
- Seed

The Universe from Nothing workshop may be of use for more advanced testing scenarios involving a seed hypervisor, seed VM, and separate control and compute nodes.

### **Overcloud**

### **Preparation**

Clone the Kayobe repository:

```
git clone https://opendev.org/openstack/kayobe.git -b stable/2024.2
```

Change the current directory to the Kayobe repository:

```
cd kayobe
```

Clone the kayobe-config-dev repository to config/src/kayobe-config

Inspect the Kayobe configuration and make any changes necessary for your environment.

If you want to test bare metal compute nodes as described in *Bare Metal Compute*, enable Ironic by adding the following to config/src/kayobe-config/etc/kayobe/kolla.yml:

```
kolla_enable_ironic: True
```

If using Vagrant, follow the steps in *Vagrant* to prepare your environment for use with Vagrant and bring up a Vagrant VM.

If not using Vagrant, the default development configuration expects the presence of a bridge interface on the OpenStack controller host to carry control plane traffic. The bridge should be named breth1 with a single port dummy1, and an IP address of 192.168.33.3/24. This can be modified by editing config/src/kayobe-config/etc/kayobe/inventory/group\_vars/controllers/network-interfaces.

This can be added using the following commands:

```
sudo ip 1 add breth1 type bridge
sudo ip 1 set breth1 up
sudo ip a add 192.168.33.3/24 dev breth1
sudo ip 1 add dummy1 type dummy
sudo ip 1 set dummy1 up
sudo ip 1 set dummy1 master breth1
```

# Configuration

### **Enable TLS**

Apply the following configuration if you wish to enable TLS for the OpenStack API:

Set the following option in config/src/kayobe-config/etc/kayobe/kolla.yml:

```
kolla_enable_tls_internal: "yes"
```

Set the following options in config/src/kayobe-config/etc/kayobe/kolla/globals.yml:

## **Usage**

If using Vagrant, SSH into the Vagrant VM and change to the shared directory:

```
vagrant ssh
cd /vagrant
```

If not using Vagrant, run the dev/install-dev.sh script to install Kayobe and its dependencies in a Python virtual environment:

./dev/install-dev.sh

### Note

This will create an *editable install*. It is also possible to install Kayobe in a non-editable way, such that changes will not been seen until you reinstall the package. To do this you can run ./dev/install. sh.

If you are using TLS and wish to generate self-signed certificates:

```
export KAYOBE_OVERCLOUD_GENERATE_CERTIFICATES=1
```

Run the dev/overcloud-deploy. sh script to deploy the OpenStack control plane:

```
./dev/overcloud-deploy.sh
```

Upon successful completion of this script, the control plane will be active.

## **Testing**

Scripts are provided for testing the creation of virtual and bare metal instances.

## **Virtual Machines**

The control plane can be tested by running the dev/overcloud-test-vm.sh script. This will run the init-runonce setup script provided by Kolla Ansible that registers images, networks, flavors etc. It will then deploy a virtual server instance, and delete it once it becomes active:

```
./dev/overcloud-test-vm.sh
```

## **Bare Metal Compute**

For a control plane with Ironic enabled, a bare metal instance can be deployed. We can use the Tenks project to create fake bare metal nodes.

Clone the tenks repository:

```
git clone https://opendev.org/openstack/tenks.git
```

Optionally, edit the Tenks configuration file, dev/tenks-deploy-config-compute.yml.

Run the dev/tenks-deploy-compute.sh script to deploy Tenks:

```
/dev/tenks-denlov-compute.sh /tenks
```

Check that Tenks has created VMs called tk0 and tk1:

```
sudo virsh list --all
```

Verify that VirtualBMC is running:

```
~/tenks-venv/bin/vbmc list
```

Configure the firewall to allow the baremetal nodes to access OpenStack services:

```
./dev/configure-firewall.sh
```

We are now ready to run the dev/overcloud-test-baremetal.sh script. This will run the init-runonce setup script provided by Kolla Ansible that registers images, networks, flavors etc. It will then deploy a bare metal server instance, and delete it once it becomes active:

```
./dev/overcloud-test-baremetal.sh
```

The machines and networking created by Tenks can be cleaned up via dev/tenks-teardown-compute. sh:

```
./dev/tenks-teardown-compute.sh ./tenks
```

# **Upgrading**

It is possible to test an upgrade from a previous release by running the dev/overcloud-upgrade.sh script:

```
./dev/overcloud-upgrade.sh
```

#### Seed

These instructions cover deploying the seed services directly rather than in a VM.

# **Preparation**

Clone the Kayobe repository:

```
git clone https://opendev.org/openstack/kayobe.git -b stable/2024.2
```

Change to the kayobe directory:

```
cd kayobe
```

Clone the kayobe-config-dev repository to config/src/kayobe-config:

Inspect the Kayobe configuration and make any changes necessary for your environment.

The default development configuration expects the presence of a bridge interface on the seed host to carry provisioning traffic. The bridge should be named breth1 with a single port eth1, and an IP

address of 192.168.33.5/24. This can be modified by editing config/src/kayobe-config/etc/kayobe/inventory/group\_vars/seed/network-interfaces. Alternatively, this can be added using the following commands:

```
sudo ip 1 add breth1 type bridge
sudo ip 1 set breth1 up
sudo ip a add 192.168.33.5/24 brd 192.168.33.255 dev breth1
sudo ip 1 add dummy1 type dummy
sudo ip 1 set dummy1 up
sudo ip 1 set dummy1 master breth1
```

## **Usage**

Run the dev/install.sh script to install Kayobe and its dependencies in a Python virtual environment:

```
./dev/install.sh
```

Run the dev/seed-deploy.sh script to deploy the seed services:

```
export KAYOBE_SEED_VM_PROVISION=0
./dev/seed-deploy.sh
```

Upon successful completion of this script, the seed will be active.

# **Testing**

The seed services may be tested using the Tenks project to create fake bare metal nodes.

If your seed has a non-standard MTU, you should set it via aio\_mtu in etc/kayobe/networks.yml.

Clone the tenks repository:

```
git clone https://opendev.org/openstack/tenks.git
```

Optionally, edit the Tenks configuration file, dev/tenks-deploy-config-overcloud.yml.

Run the dev/tenks-deploy-overcloud.sh script to deploy Tenks:

```
./dev/tenks-deploy-overcloud.sh ./tenks
```

Check that Tenks has created a VM called controller0:

```
sudo virsh list --all
```

Verify that VirtualBMC is running:

```
~/tenks-venv/bin/vbmc list
```

It is now possible to discover, inspect and provision the controller VM:

```
source dev/environment-setup.sh
kayobe overcloud inventory discover
kayobe overcloud hardware inspect
kayobe overcloud provision
```

The controller VM is now accessible via SSH as the bootstrap user (centos or ubuntu) at 192.168. 33.3.

The machines and networking created by Tenks can be cleaned up via dev/tenks-teardown-overcloud.sh:

```
./dev/tenks-teardown-overcloud.sh ./tenks
```

# **Upgrading**

It is possible to test an upgrade by running the dev/seed-upgrade.sh script:

```
./dev/seed-upgrade.sh
```

# **Testing**

Kayobe has a number of test suites covering different areas of code. Many tests are run in virtual environments using tox.

# **Preparation**

## **System Prerequisites**

The following packages should be installed on the development system prior to running kayobes tests.

• Ubuntu/Debian:

```
sudo apt-get install build-essential python3-dev libssl-dev python3-pip

→git
```

• Fedora or CentOS Stream 9/Rocky 9/RHEL 9:

```
sudo dnf install python3-devel openssl-devel python3-pip git gcc
```

• OpenSUSE/SLE 12:

```
sudo zypper install python3-devel python3-pip libopenssl-devel git
```

# **Python Prerequisites**

If your distro has at least tox 1.8, use your system package manager to install the python-tox package. Otherwise install this on all distros:

```
sudo pip install -U tox
```

You may need to explicitly upgrade virtualenv if youve installed the one from your OS distribution and it is too old (tox will complain). You can upgrade it individually, if you need to:

```
sudo pip install -U virtualenv
```

## **Running Unit Tests Locally**

If you havent already, the kayobe source code should be pulled directly from git:

```
# from your home or source directory
cd ~
git clone https://opendev.org/openstack/kayobe.git -b stable/2024.2
cd kayobe
```

# **Running Unit and Style Tests**

Kayobe defines a number of different tox environments in tox.ini. The default environments may be displayed:

```
tox -list
```

To run all default environments:

```
_____
```

To run one or more specific environments, including any of the non-default environments:

```
tox -e <environment>[.<environment>]
```

## **Environments**

The following tox environments are provided:

#### alint

Run Ansible linter.

### ansible

Run Ansible tests for some ansible roles using Ansible playbooks.

# ansible-syntax

Run a syntax check for all Ansible files.

## docs

Build Sphinx documentation.

### molecule

Run Ansible tests for some Ansible roles using the molecule test framework.

### pep8

Run style checks for all shell, python and documentation files.

py3

Run python unit tests for kayobe python module.

# **Writing Tests**

### **Unit Tests**

Unit tests follow the lead of OpenStack, and use unittest. One difference is that tests are run using the discovery functionality built into unittest, rather than ostestr/stestr. Unit tests are found in kayobe/tests/unit/, and should be added to cover all new python code.

#### **Ansible Role Tests**

Two types of test exist for Ansible roles - pure Ansible and molecule tests.

### **Pure Ansible Role Tests**

These tests exist for the kolla-ansible role, and are found in ansible/<role>/tests/\*.yml. The role is exercised using an ansible playbook.

#### **Molecule Role Tests**

Molecule is an Ansible role testing framework that allows roles to be tested in isolation, in a stable environment, under multiple scenarios. Kayobe uses Docker engine to provide the test environment, so this must be installed and running on the development system.

Molecule scenarios are found in ansible/<role>/molecule/<scenario>, and defined by the config file ansible/<role>/molecule/<scenario>/molecule.yml Tests are written in python using the pytest framework, and are found in ansible/<role>/molecule/<scenario>/tests/test\_\*.py.

Molecule tests currently exist for the kolla-openstack role, and should be added for all new roles where practical.

### Release notes

Kayobe (just like Kolla) uses the following release notes sections:

- features for new features or functionality; these should ideally refer to the blueprint being implemented;
- fixes for fixes closing bugs; these must refer to the bug being closed;

- upgrade for notes relevant when upgrading from previous version; these should ideally be added only between major versions; required when the proposed change affects behaviour in a non-backwards compatible way or generally changes something impactful;
- deprecations to track deprecated features; relevant changes may consist of only the commit message and the release note;
- prelude filled in by the PTL before each release or RC.

Other release note types may be applied per common sense. Each change should include a release note unless being a TrivialFix change or affecting only docs or CI. Such changes should *not* include a release note to avoid confusion. Remember release notes are mostly for end users which, in case of Kolla, are OpenStack administrators/operators. In case of doubt, the core team will let you know what is required.

To add a release note, run the following command:

```
tox -e venv -- reno new <summary-line-with-dashes>
```

All release notes can be inspected by browsing releasenotes/notes directory.

To generate release notes in HTML format in releasenotes/build, run:

```
tox -e releasenotes
```

Note this requires the release note to be tracked by git so you have to at least add it to the gits staging area.

## Releases

This guide is intended to complement the OpenStack releases site, and the project team guides section on release management.

Team members make themselves familiar with the release schedule for the current release, for example https://releases.openstack.org/train/schedule.html.

### **Release Model**

As a deployment project, Kayobes release model differs from many other OpenStack projects. Kayobe follows the cycle-trailing release model, to allow time after the OpenStack coordinated release to wait for distribution packages and support new features. This gives us three months after the final release to prepare our final releases. Users are typically keen to try out the new release, so we should aim to release as early as possible while ensuring we have confidence in the release.

#### Release Schedule

While we dont wish to repeat the OpenStack release documentation, we will point out the high level schedule, and draw attention to areas where our process is different.

### **Milestones**

At each of the various release milestones, pay attention to what other projects are doing.

### **Feature Freeze**

As with projects following the common release model, Kayobe uses a feature freeze period to allow the code to stabilise prior to release. There is no official feature freeze date for the cycle-trailing model, but we typically freeze around **three weeks** after the common feature freeze. During this time, no features should be merged to the master branch.

### **Before RC1**

Prior to creating a release candidate and stable branch, the following tasks should be performed.

## **Testing**

Test the code and fix at a minimum all critical issues.

Remember to use the check experimental review comment on a Gerrit change to trigger jobs in the experimental pipeline, which provide increased test coverage.

## Synchronise with Kolla Ansible feature flags

Clone the Kolla Ansible repository, and run the Kayobe tools/kolla-feature-flags.sh script:

```
tools/kolla-feature-flags.sh <path to kolla-ansible source>
```

Copy the output of the script, and replace the kolla\_feature\_flags list in ansible/roles/kolla-ansible/vars/main.yml.

The kolla.yml configuration file should be updated to match:

```
tools/feature-flags.py
```

Copy the output of the script, and replace the list of kolla\_enable\_\* flags in etc/kayobe/kolla.yml.

# Synchronise with Kolla Ansible inventory

Clone the Kolla Ansible repository, and copy across any relevant changes. The Kayobe inventory is based on the ansible/inventory/multinode inventory, but split into 3 parts - top-level, components and services.

# Top level

The top level inventory template is ansible/roles/kolla-ansible/templates/overcloud-top-level.j2. It is heavily templated, and does not typically need to be changed. Look out for changes in the multinode inventory before the [baremetal] group.

## **Components**

The components inventory template is ansible/roles/kolla-ansible/templates/overcloud-components.j2.

This includes groups in the multinode inventory from the [baremetal] group down to the following text:

# Additional control implemented here. These groups allow you to control which # services run on which hosts at a per-service level.

## **Services**

The services inventory template is ansible/roles/kolla-ansible/templates/overcloud-services.j2.

This includes groups in the multinode inventory from the following text to the end of the file:

# Additional control implemented here. These groups allow you to control which # services run on which hosts at a per-service level.

There are some small changes in this section which should be maintained.

# Update dependencies to upcoming release

Prior to the release, we update the dependencies and upper constraints on the master branch to use the upcoming release. This is now quite easy to do, following the introduction of the openstack\_release variable. This is done prior to creating a release candidate. For example, see https://review.opendev.org/c/openstack/kayobe/+/867617.

# Synchronise kayobe-config

Ensure that configuration defaults in kayobe-config are in sync with those under etc/kayobe in kayobe. This can be done via:

rsync -a --delete kayobe/etc/kayobe/ kayobe-config/etc/kayobe

Commit the changes and submit for review.

# Synchronise kayobe-config-dev

Ensure that configuration defaults in kayobe-config-dev are in sync with those in kayobe-config. This requires a little more care, since some configuration options have been changed from the defaults. Choose a method to suit you and be careful not to lose any configuration.

Commit the changes and submit for review.

# Prepare release notes

Its possible to add a prelude to the release notes for a particular release using a prelude section in a reno note.

Ensure that release notes added during the release cycle are tidy and consistent. The following command is useful to list release notes added this cycle:

git diff --name-only origin/stable/<previous release> -- releasenotes/

# RC1

Prior to cutting a stable branch, the master branch should be tagged as a release candidate. This allows the reno tool to determine where to stop searching for release notes for the next release. The tag should take the following form: <release tag>.0rc\$n, where \$n is the release candidate number.

This should be done for each deliverable using the releases tooling. A release candidate and stable branch definitions should be added for each Kayobe deliverable (kayobe, kayobe-config, kayobe-config-dev). These are defined in deliverables/<release name>/kayobe.yaml. Currently the same version is used for each deliverable.

The changes should be proposed to the releases repository. For example: https://review.opendev.org/#/c/700174.

#### After RC1

The OpenStack proposal bot will propose changes to the new branch and the master branch. These need to be approved.

After the stable branch has been cut, the master branch can be unfrozen and development on features for the next release can begin. At this point it will still be using dependencies and upper constraints from the release branch, so revert the patch created in *Update dependencies to upcoming release*. For example, see https://review.opendev.org/701747.

Finally, set the previous release used in upgrade jobs to the new release. For example, see https://review.opendev.org/709145.

### RC2+

Further release candidates may be created on the stable branch as necessary in a similar manner to RC1.

#### **Final Releases**

A release candidate may be promoted to a final release if it has no critical bugs against it.

Tags should be created for each deliverable (kayobe, kayobe-config, kayobe-config-dev). Currently the same version is used for each.

The changes should be proposed to the releases repository. For example: https://review.opendev.org/701724.

### Post-release activites

An email will be sent to the release-announce mailing list about the new release.

# **Continuing Development**

Search for TODOs in the codebases describing tasks to be performed during the next release cycle.

Dates for each milestone in the new cycle can be found in Kolla projects documentation. The first action that needs to be taken is to switch Kayobe back to using the master version of its dependencies (R-23).

### **Stable Releases**

Stable branch releases should be made periodically for each supported stable branch, no less than once every 45 days.