

connect_volume (*connection_properties*)

Attach the volume to instance_name.

Parameters **connection_properties** (*dict*) The valid dictionary that describes all of the target volume attributes.

Returns dict

connection_properties for iSCSI must include: target_portal(s) - ip and optional port target_iqn(s) - iSCSI Qualified Name target_lun(s) - LUN id of the volume Note that plural keys may be used when use_multipath=True

disconnect_volume (*connection_properties*, *device_info*, *force=False*, *ignore_errors=False*)
Detach the volume from instance_name.

Parameters

- **connection_properties** (*dict that must include: target_portal(s) - IP and optional port target_iqn(s) - iSCSI Qualified Name target_lun(s) - LUN id of the volume*) The dictionary that describes all of the target volume attributes.
- **device_info** (*dict*) historical difference, but same as connection_props
- **force** (*bool*) Whether to forcefully disconnect even if flush fails.
- **ignore_errors** (*bool*) When force is True, this will decide whether to ignore errors or raise an exception once finished the operation. Default is False.

```
class os_brick.initiator.connector.FibreChannelConnector (root_helper,  
                                                         driver=None,  
                                                         exe-  
                                                         cute=None,  
                                                         use_multipath=False,  
                                                         de-  
                                                         vice_scan_attempts=3,  
                                                         *args,  
                                                         **kwargs)
```

Connector class to attach/detach Fibre Channel volumes.

connect_volume (*connection_properties*)

Attach the volume to instance_name.

Parameters **connection_properties** (*dict*) The dictionary that describes all of the target volume attributes.

Returns dict

connection_properties for Fibre Channel must include: target_wwn - World Wide Name target_lun - LUN id of the volume

disconnect_volume (*connection_properties*, *device_info*, *force=False*, *ignore_errors=False*)
Detach the volume from instance_name.

Parameters

- **connection_properties** (*dict*) The dictionary that describes all of the target volume attributes.
- **device_info** (*dict*) historical difference, but same as connection_props

connection_properties for Fibre Channel must include: target_wwn - World Wide Name
target_lun - LUN id of the volume

```
class os_brick.initiator.connector.LocalConnector (root_helper,  
                                                    driver=None, *args,  
                                                    **kwargs)
```

Connector class to attach/detach File System backed volumes.

connect_volume (*connection_properties*)

Connect to a volume.

Parameters **connection_properties** (*dict*) The dictionary that describes all of the target volume attributes. connection_properties must include:

- **device_path** - path to the volume to be connected

Returns dict

disconnect_volume (*connection_properties, device_info, force=False, ignore_errors=False*)

Disconnect a volume from the local host.

Parameters

- **connection_properties** (*dict*) The dictionary that describes all of the target volume attributes.
- **device_info** (*dict*) historical difference, but same as connection_props

```
class os_brick.initiator.connector.HuaweiStorHyperConnector (root_helper,  
                                                            driver=None,  
                                                            *args,  
                                                            **kwargs)
```

Connector class to attach/detach SDSHypervisor volumes.

connect_volume (*connection_properties*)

Connect to a volume.

Parameters **connection_properties** (*dict*) The dictionary that describes all of the target volume attributes.

Returns dict

disconnect_volume (*connection_properties, device_info, force=False, ignore_errors=False*)

Disconnect a volume from the local host.

Parameters

- **connection_properties** (*dict*) The dictionary that describes all of the target volume attributes.
- **device_info** (*dict*) historical difference, but same as connection_props

exception Exceptions

Exceptions for the Brick library.

```
class os_brick.exception.BrickException (message=None, **kwargs)  
    Base Brick Exception
```

To correctly use this class, inherit from it and define a `msg_fmt` property. That `msg_fmt` will get `printfd` with the keyword arguments provided to the constructor.

```
class os_brick.exception.NotFound (message=None, **kwargs)
```

```
class os_brick.exception.Invalid (message=None, **kwargs)
```

```
class os_brick.exception.InvalidParameterValue (message=None,  
                                                **kwargs)
```

```
class os_brick.exception.NoFibreChannelHostsFound (message=None,  
                                                    **kwargs)
```

```
class os_brick.exception.NoFibreChannelVolumeDeviceFound (message=None,  
                                                            **kwargs)
```

```
class os_brick.exception.VolumeDeviceNotFound (message=None, **kwargs)
```

```
class os_brick.exception.ProtocolNotSupported (message=None, **kwargs)
```

