

---

# **OpenStack-Ansible Documentation:**

## **os\_nova role**

***Release 18.1.0.dev551***

**OpenStack-Ansible Contributors**

**Nov 07, 2023**



# CONTENTS

<b>1</b>	<b>Configuring the Compute (nova) service (optional)</b>	<b>1</b>
1.1	Availability zones . . . . .	1
1.2	Block device tuning for Ceph (RBD) . . . . .	1
1.3	Config drive . . . . .	2
1.4	Libvirtd connectivity and authentication . . . . .	2
1.5	Multipath . . . . .	3
1.6	Shared storage and synchronized UID/GID . . . . .	3
<b>2</b>	<b>Default variables</b>	<b>5</b>
<b>3</b>	<b>Dependencies</b>	<b>23</b>
<b>4</b>	<b>Example playbook</b>	<b>25</b>
<b>5</b>	<b>Tags</b>	<b>27</b>
<b>6</b>	<b>CPU platform compatibility</b>	<b>29</b>
<b>7</b>	<b>Compute driver compatibility</b>	<b>31</b>



## CONFIGURING THE COMPUTE (NOVA) SERVICE (OPTIONAL)

The Compute service (nova) handles the creation of virtual machines within an OpenStack environment. Many of the default options used by OpenStack-Ansible are found within `defaults/main.yml` within the nova role.

### 1.1 Availability zones

Deployers with multiple availability zones can set the `nova_nova_conf_overrides.DEFAULT.default_schedule_zone` Ansible variable to specify an availability zone for new requests. This is useful in environments with different types of hypervisors, where builds are sent to certain hardware types based on their resource requirements.

For example, if you have servers running on two racks without sharing the PDU. These two racks can be grouped into two availability zones. When one rack loses power, the other one still works. By spreading your containers onto the two racks (availability zones), you will improve your service availability.

### 1.2 Block device tuning for Ceph (RBD)

Enabling Ceph and defining `nova_libvirt_images_rbd_pool` changes two libvirt configurations by default:

- `hw_disk_discard: unmap`
- `disk_cachemodes: network=writeback`

Setting `hw_disk_discard` to `unmap` in libvirt enables discard (sometimes called TRIM) support for the underlying block device. This allows reclaiming of unused blocks on the underlying disks.

Setting `disk_cachemodes` to `network=writeback` allows data to be written into a cache on each change, but those changes are flushed to disk at a regular interval. This can increase write performance on Ceph block devices.

You have the option to customize these settings using two Ansible variables (defaults shown here):

```
nova_libvirt_hw_disk_discard: 'unmap'  
nova_libvirt_disk_cachemodes: 'network=writeback'
```

You can disable discard by setting `nova_libvirt_hw_disk_discard` to `ignore`. The `nova_libvirt_disk_cachemodes` can be set to an empty string to disable `network=writeback`.

The following minimal example configuration sets nova to use the `ephemeral-vms` Ceph pool. The following example uses cephx authentication, and requires an existing `cinder` account for the `ephemeral-vms` pool:

```
nova_libvirt_images_rbd_pool: ephemeral-vms
ceph_mons:
  - 172.29.244.151
  - 172.29.244.152
  - 172.29.244.153
```

If you have a different Ceph username for the pool, use it as:

```
cinder_ceph_client: <ceph-username>
```

- The Ceph documentation for OpenStack has additional information about these settings.
- [OpenStack-Ansible and Ceph Working Example](#)

## 1.3 Config drive

By default, OpenStack-Ansible does not configure nova to force config drives to be provisioned with every instance that nova builds. The metadata service provides configuration information that is used by `cloud-init` inside the instance. Config drives are only necessary when an instance does not have `cloud-init` installed or does not have support for handling metadata.

A deployer can set an Ansible variable to force config drives to be deployed with every virtual machine:

```
nova_nova_conf_overrides:
  DEFAULT:
    force_config_drive: True
```

Certain formats of config drives can prevent instances from migrating properly between hypervisors. If you need forced config drives and the ability to migrate instances, set the config drive format to `vfat` using the `nova_nova_conf_overrides` variable:

```
nova_nova_conf_overrides:
  DEFAULT:
    config_drive_format: vfat
    force_config_drive: True
```

## 1.4 Libvirtd connectivity and authentication

By default, OpenStack-Ansible configures the libvirt daemon in the following way:

- TLS connections are enabled
- TCP plaintext connections are disabled
- Authentication over TCP connections uses SASL

You can customize these settings using the following Ansible variables:

```
# Enable libvирtd's TLS listener
nova_libvirtd_listen_tls: 1

# Disable libvирtd's plaintext TCP listener
nova_libvirtd_listen_tcp: 0

# Use SASL for authentication
nova_libvirtd_auth_tcp: sasl
```

## 1.5 Multipath

Nova supports multipath for iSCSI-based storage. Enable multipath support in nova through a configuration override:

```
nova_nova_conf_overrides:
    libvirt:
        iscsi_use_multipath: true
```

## 1.6 Shared storage and synchronized UID/GID

Specify a custom UID for the nova user and GID for the nova group to ensure they are identical on each host. This is helpful when using shared storage on Compute nodes because it allows instances to migrate without filesystem ownership failures.

By default, Ansible creates the nova user and group without specifying the UID or GID. To specify custom values for the UID or GID, set the following Ansible variables:

```
nova_system_user_uid = <specify a UID>
nova_system_group_gid = <specify a GID>
```

**Warning:** Setting this value after deploying an environment with OpenStack-Ansible can cause failures, errors, and general instability. These values should only be set once before deploying an OpenStack environment and then never changed.

**tags** openstack, nova, cloud, ansible

**category** \*nix

**This role will install the following Systemd services:**

- nova-server
- nova-compute

To clone or view the source code for this repository, visit the role repository for os\_nova.



## DEFAULT VARIABLES

```
# Enable/Disable barbican configurations
nova_barbican_enabled: "{{ (groups['barbican_all'] is defined) and (groups["
    ↪'barbican_all'] | length > 0) }}"
# Enable/Disable designate configurations
nova_designate_enabled: "{{ (groups['designate_all'] is defined) and (groups["
    ↪'designate_all'] | length > 0) }}"
# Notification topics for designate.
nova_notifications_designate: notifications_designate
# Enable/Disable ceilometer configurations
nova_ceilometer_enabled: "{{ (groups['ceilometer_all'] is defined) and_
    ↪(groups['ceilometer_all'] | length > 0) }}"
# Enable/Disable nova versioned notification
nova_versioned_notification_enabled: False

nova_memcached_servers: "{{ memcached_servers }}"

## Verbosity Options
debug: False

# Set the host which will execute the shade modules
# for the service setup. The host must already have
# clouds.yaml properly configured.
nova_service_setup_host: "{{ openstack_service_setup_host | default('localhost'
    ↪') }}"
nova_service_setup_host_python_interpreter: "{{ openstack_service_setup_host_"
    ↪python_interpreter | default((nova_service_setup_host == 'localhost') |_
    ↪ternary(ansible_playbook_python, ansible_facts['python']['executable'])) }}"

# Set the host which will run compute initialization tasks such as checking
# for a compute node to be up and running cell discovery.
nova_conductor_setup_host: "{{ groups[nova_services['nova-conductor']]['group"
    ↪'][0] }}"
# Set the package install state for distribution packages
# Options are 'present' and 'latest'
nova_package_state: "{{ package_state | default('latest') }}"
# Set installation method.
```

(continues on next page)

(continued from previous page)

```

nova_install_method: "{{ service_install_method | default('source') }}"
nova_venv_python_executable: "{{ openstack_venv_python_executable | default(
    ~'python3') }}"

nova_git_repo: https://opendev.org/openstack/nova
nova_git_install_branch: master

nova_upper_constraints_url: "{{ requirements_git_url | default('https://
    ~releases.openstack.org/constraints/upper/' ~ requirements_git_install_
    ~branch | default('master')) }}"
nova_git_constraints:
  - --constraint {{ nova_upper_constraints_url }}
nova_pip_install_args: "{{ pip_install_options | default('') }}"

# Name of the virtual env to deploy into
nova_venv_tag: "{{ venv_tag | default('untagged') }}"
nova_bin: "{{ _nova_bin }}"

## Nova user information
nova_system_user_name: nova
nova_system_group_name: nova
nova_system_shell: /bin/bash
nova_system_comment: nova system user
nova_system_home_folder: "/var/lib/{{ nova_system_user_name }}"
nova_system_slice_name: nova
nova_libvirt_save_path: "{{ nova_system_home_folder }}/save"

nova_lock_dir: "{{ openstack_lock_dir | default('/run/lock') }}"

nova_management_address: "127.0.0.1"

## Manually specified nova UID/GID
# Deployers can specify a UID for the nova user as well as the GID for the
# nova group if needed. This is commonly used in environments where shared
# storage is used, such as NFS or GlusterFS, and nova UID/GID values must be
# in sync between multiple servers.
#
# WARNING: Changing these values on an existing deployment can lead to
# failures, errors, and instability.
#
# nova_system_user_uid = <UID>
# nova_system_group_gid = <GID>

## Database info
nova_db_setup_host: "{{ openstack_db_setup_host | default('localhost') }}"
nova_db_setup_python_interpreter: "{{ openstack_db_setup_python_interpreter |_
    ~default((nova_db_setup_host == 'localhost') | ternary(ansible_playbook_
    ~python, ansible_facts['python']['executable'])) }}"
nova_galera_address: "{{ galera_address | default('127.0.0.1') }}"

```

(continues on next page)

(continued from previous page)

```

nova_galera_user: nova
nova_galera_database: nova
nova_db_max_overflow: "{{ openstack_db_max_overflow | default('50') }}"
nova_db_max_pool_size: "{{ openstack_db_max_pool_size | default('5') }}"
nova_db_pool_timeout: "{{ openstack_db_pool_timeout | default('30') }}"
nova_db_connection_recycle_time: "{{ openstack_db_connection_recycle_time |_
    ~default('600') }}"
nova_galera_port: "{{ galera_port | default('3306') }}"
# Toggle whether nova connects via an encrypted connection
nova_galera_use_ssl: "{{ galera_use_ssl | default(False) }}"
# The path where to store the database server CA certificate
nova_galera_ssl_ca_cert: "{{ galera_ssl_ca_cert | default('') }}"

## DB API
nova_api_galera_address: "{{ nova_galera_address }}"
nova_api_galera_user: nova_api
nova_api_galera_database: nova_api
nova_api_galera_port: "{{ galera_port | default('3306') }}"
nova_api_db_max_overflow: "{{ openstack_db_max_overflow | default('50') }}"
nova_api_db_max_pool_size: "{{ openstack_db_max_pool_size | default('5') }}"
nova_api_db_pool_timeout: "{{ openstack_db_pool_timeout | default('30') }}"
nova_api_db_connection_recycle_time: "{{ openstack_db_connection_recycle_time |_
    ~| default('600') }}"

## DB Cells
nova_cell0_database: "nova_cell0"
nova_cell1_name: "cell1"

## Oslo Messaging

# RabbitMQ
nova_oslomsg_heartbeat_in_pthread: "{{ oslomsg_heartbeat_in_pthread |_
    ~default(_nova_oslomsg_heartbeat_in_pthread) }}"

# RPC
nova_oslomsg_rpc_host_group: "{{ oslomsg_rpc_host_group | default('rabbitmq_'
    ~'all') }}"
nova_oslomsg_rpc_setup_host: "{{ (nova_oslomsg_rpc_host_group in groups) |_
    ~ternary(groups[nova_oslomsg_rpc_host_group][0], 'localhost') }}"
nova_oslomsg_rpc_transport: "{{ oslomsg_rpc_transport | default('rabbit') }}"
nova_oslomsg_rpc_servers: "{{ oslomsg_rpc_servers | default('127.0.0.1') }}"
nova_oslomsg_rpc_port: "{{ oslomsg_rpc_port | default('5672') }}"
nova_oslomsg_rpc_use_ssl: "{{ oslomsg_rpc_use_ssl | default(False) }}"
nova_oslomsg_rpc_userid: nova
nova_oslomsg_rpc_vhost: /nova
nova_oslomsg_rpc_ssl_version: "{{ oslomsg_rpc_ssl_version | default('TLSv1_2'
    ~') }}"
nova_oslomsg_rpc_ssl_ca_file: "{{ oslomsg_rpc_ssl_ca_file | default('') }}"

```

(continues on next page)

(continued from previous page)

```

# Notify
nova_oslomsg_notify_host_group: "{{ oslomsg_notify_host_group | default(
    'rabbitmq_all') }}"
nova_oslomsg_notify_setup_host: "{{ (nova_oslomsg_notify_host_group in_
    groups) | ternary(groups[nova_oslomsg_notify_host_group][0], 'localhost') }}"
nova_oslomsg_notify_transport: "{{ oslomsg_notify_transport | default('rabbit
    ') }}"
nova_oslomsg_notify_servers: "{{ oslomsg_notify_servers | default('127.0.0.1
    ') }}"
nova_oslomsg_notify_port: "{{ oslomsg_notify_port | default('5672') }}"
nova_oslomsg_notify_use_ssl: "{{ oslomsg_notify_use_ssl | default(False) }}"
nova_oslomsg_notify_userid: "{{ nova_oslomsg_rpc_userid }}"
nova_oslomsg_notify_password: "{{ nova_oslomsg_rpc_password }}"
nova_oslomsg_notify_vhost: "{{ nova_oslomsg_rpc_vhost }}"
nova_oslomsg_notify_ssl_version: "{{ oslomsg_notify_ssl_version | default(
    'TLSv1_2') }}"
nova_oslomsg_notify_ssl_ca_file: "{{ oslomsg_notify_ssl_ca_file | default('')_|_
    }}"

## Qdrouterd info
# TODO(ansmith): Change structure when more backends will be supported
nova_oslomsg_amqp1_enabled: "{{ nova_oslomsg_rpc_transport == 'amqp' }}"

## Nova virtualization Types
# The nova_virt_types dictionary contains global overrides used for
# specific compute types. Every variable inside of this dictionary
# will become an ansible fact. This gives the user the option to set
# or customize things based on their needs without having to redefine
# this entire data structure. Every supported compute type will be
# have its specific variable requirements set under its short name.
nova_virt_types:
  ironic:
    nova_compute_driver: ironic.IronicDriver
    nova_reserved_host_memory_mb: 0
    nova_scheduler_tracks_instance_changes: False
  kvm:
    nova_compute_driver: libvirt.LibvirtDriver
    nova_reserved_host_memory_mb: 2048
    nova_scheduler_tracks_instance_changes: True
  qemu:
    nova_compute_driver: libvirt.LibvirtDriver
    nova_reserved_host_memory_mb: 2048
    nova_scheduler_tracks_instance_changes: True
    nova_cpu_mode: "none"

# If this is not set, then the playbook will try to guess it.
#nova_virt_type: kvm

```

(continues on next page)

(continued from previous page)

```

# Enable Kernel Shared Memory (KSM)
nova_compute_ksm_enabled: False

#if set, nova_virt_type must be one of these:
nova_supported_virt_types:
    - qemu
    - kvm
    - ironic

## Nova Auth
nova_service_region: "{{ service_region | default('RegionOne') }}"
nova_service_project_name: "service"
nova_service_project_domain_id: default
nova_service_user_domain_id: default
nova_service_user_name: "nova"
nova_service_role_names:
    - admin
    - service
nova_service_token_roles:
    - service
nova_service_token_roles_required: "{{ openstack_service_token_roles_required | default(True) }}"

## Keystone authentication middleware
nova_keystone_auth_plugin: password

## Nova enabled apis
nova_enabled_apis: "osapi_compute,metadata"

## Domain name used to configure FQDN for instances. When empty, only the
## hostname without
## a domain will be configured.
nova_dhcp_domain: "{{ dhcp_domain | default('') }}"

## Nova v2.1
nova_service_name: nova
nova_service_type: compute
nova_service_proto: http
nova_service_publicuri_proto: "{{ openstack_service_publicuri_proto | default(nova_service_proto) }}"
nova_service_adminuri_proto: "{{ openstack_service_adminuri_proto | default(nova_service_proto) }}"
nova_service_internaluri_proto: "{{ openstack_service_internaluri_proto | default(nova_service_proto) }}"
nova_service_bind_address: "{{ openstack_service_bind_address | default('0.0.0.0') }}"
nova_service_port: 8774
nova_service_description: "Nova Compute Service"

```

(continues on next page)

(continued from previous page)

```

nova_service_publicuri: "{{ nova_service_publicuri_proto }}://{{ external_lb_ \
→vip_address }}:{{ nova_service_port }}"
nova_service_publicurl: "{{ nova_service_publicuri }}/v2.1"
nova_service_adminuri: "{{ nova_service_adminuri_proto }}://{{ internal_lb_ \
→vip_address }}:{{ nova_service_port }}"
nova_service_adminurl: "{{ nova_service_adminuri }}/v2.1"
nova_service_internaluri: "{{ nova_service_internaluri_proto }}://{{ internal_ \
→lb_vip_address }}:{{ nova_service_port }}"
nova_service_internalurl: "{{ nova_service_internaluri }}/v2.1"

## Nova spice
nova_spice_html5proxy_base_proto: "{{ openstack_service_publicuri_proto | \
→default('http') }}"
nova_spice_html5proxy_base_port: 6082
nova_spice_html5proxy_base_uri: "{{ nova_spice_html5proxy_base_proto }}://{{ \
→external_lb_vip_address }}:{{ nova_spice_html5proxy_base_port }}"
nova_spice_html5proxy_base_url: "{{ nova_spice_html5proxy_base_uri }}/spice_ \
→auto.html"
nova_spice_console_agent_enabled: True
nova_spicehtml5_git_repo: "{{ spicehtml5_git_repo | default('https://gitlab. \
→freedesktop.org/spice/spice-html5.git') }}"
nova_spicehtml5_git_install_branch: "{{ spicehtml5_git_install_branch | \
→default('master') }"

## Nova novnc
nova_novncproxy_proto: "{{ openstack_service_publicuri_proto | default('http' \
→) }}"
nova_novncproxy_port: 6080
nova_novncproxy_host: "{{ openstack_service_bind_address | default('0.0.0.0') }}"
nova_novncproxy_base_uri: "{{ nova_novncproxy_proto }}://{{ external_lb_vip_ \
→address }}:{{ nova_novncproxy_port }}"
nova_novncproxy_base_url: "{{ nova_novncproxy_base_uri }}/vnc_lite.html"
nova_novncproxy_vncserver_proxyclient_address: "{{ (nova_management_address_ \
→== 'localhost') | ternary('127.0.0.1', nova_management_address) }}"
nova_novncproxy_vncserver_listen: "{{ (nova_management_address == 'localhost' \
→) | ternary('127.0.0.1', nova_management_address) }}"
nova_novncproxy_git_repo: "{{ novncproxy_git_repo | default('https://github. \
→com/novnc/noVNC') }}"
nova_novncproxy_git_install_branch: "{{ novncproxy_git_install_branch | \
→default('master') }"

## Nova serialconsole
nova_serialconsoleproxy_proto: "ws"
nova_serialconsoleproxy_port: 6083
nova_serialconsoleproxy_port_range: 10000:20000
nova_serialconsoleproxy_base_uri: "{{ nova_serialconsoleproxy_proto }}://{{ \
→external_lb_vip_address }}:{{ nova_serialconsoleproxy_port }}"
nova_serialconsoleproxy_base_url: "{{ nova_serialconsoleproxy_base_uri }}"

```

(continues on next page)

(continued from previous page)

```

nova_serialconsoleproxy_serialconsole_proxyserver_proxyclient_address: "{{
  ↪ansible_host }}"

## Nova metadata
nova_metadata_proxy_enabled: "{{ nova_network_services[nova_network_type][
  ↪'metadata_proxy_enabled'] | bool }}"
nova_metadata_bind_address: "{{ openstack_service_bind_address | default('0.0.
  ↪0.0') }}"
nova_metadata_port: 8775

## Nova compute
nova_nested_virt_enabled: False

# Uwsgi settings
nova_wsgi_processes_max: 16
nova_wsgi_processes: "{{ [[ansible_facts['processor_vcpus']]|default(1), 1] |_
  ↪max * 2, nova_wsgi_processes_max] | min }}"
nova_wsgi_threads: 1

## Nova libvirt
# Warning: If nova_libvirt_inject_key or nova_libvirt_inject_password are
# enabled for Ubuntu compute hosts
# then the kernel will be made readable to nova user (a requirement for
# libguestfs).
# See Launchpad bugs 1507915 (Nova), 759725 (Ubuntu), and http://libguestfs.
# org/guestfs-faq.1.html
nova_libvirt_inject_key: False
# inject partition options:
# -2 => disable, -1 => inspect (libguestfs only), 0 => not partitioned, >0 =>
# partition number
nova_libvirt_inject_partition: -2
nova_libvirt_inject_password: False
nova_libvirt_disk_cachemodes: '{{ (nova_libvirt_images_rbd_pool | length > 0) |
  ↪| ternary("network=writeback", "") }}'
nova_libvirt_hw_disk_discard: '{{ (nova_libvirt_images_rbd_pool | length > 0) |
  ↪| ternary("unmap", "ignore") }}'
nova_libvirt_live_migration_inbound_addr: '{{ (nova_management_address ==
  ↪"localhost") | ternary("127.0.0.1", nova_management_address) }}'

## Nova console
# Set the console type. Presently the only options are ["spice", "novnc",
# "serialconsole", "disabled"].
nova_console_type: "{{ (ansible_facts['architecture'] == 'aarch64') | ternary(
  ↪'serialconsole', 'novnc') }}"

# Nova console ssl info, presently only used by novnc console type
nova_console_ssl_dir: "/etc/nova/ssl"
nova_console_ssl_cert: "{{ nova_console_ssl_dir }}/nova-console.pem"
nova_console_ssl_key: "{{ nova_console_ssl_dir }}/nova-console.key"

```

(continues on next page)

(continued from previous page)

```

# Enable TLS on VNC connection from novnc to compute hosts
nova_qemu_vnc_tls: 1
nova_vncrypt_client_key: "/etc/pki/nova-novncproxy/client-key.pem"
nova_vncrypt_client_cert: "/etc/pki/nova-novncproxy/client-cert.pem"
nova_vncrypt_ca_certs: "/etc/pki/nova-novncproxy/ca-cert.pem"
# The auth_schemes values should be listed in order of preference.
# If enabling VeNCrypt on an existing deployment which already has instances
# running,
# the noVNC proxy server must initially be allowed to use vncrypt and none.
# Once it is confirmed that all Compute nodes have VeNCrypt enabled for VNC,
# it is possible to remove the none option from the list
nova_vncrypt_auth_scheme: "vncrypt,none"

## Nova global config
nova_image_cache_manager_interval: 0

nova_network_type: linuxbridge

nova_network_services:
    linuxbridge:
        use_forwarded_for: False
        metadata_proxy_enabled: True
    nuage:
        use_forwarded_for: True
        metadata_proxy_enabled: True
        ovs_bridge: alubr0
    calico:
        use_forwarded_for: True
        metadata_proxy_enabled: False
    nsx:
        use_forwarded_for: True
        metadata_proxy_enabled: True
        ovs_bridge: nsx-managed

# Nova Scheduler
nova_cpu_allocation_ratio: 2.0
nova_disk_allocation_ratio: 1.0
nova_max_io_ops_per_host: 10
nova_ram_allocation_ratio: 1.0
nova_ram_weight_multiplier: 5.0
nova_reserved_host_disk_mb: 2048

nova_scheduler_host_subset_size: "{{ ((groups['compute_hosts'] |_
    default([]) | length) * 0.3) | round | int, 10) | min, 1) | max }}"
nova_scheduler_max_attempts: 5
nova_scheduler_default_filters:
    - ComputeFilter
    - AggregateNumInstancesFilter

```

(continues on next page)

(continued from previous page)

```

- AggregateIoOpsFilter
- ComputeCapabilitiesFilter
- ImagePropertiesFilter
- ServerGroupAntiAffinityFilter
- ServerGroupAffinityFilter
- NUMATopologyFilter

nova_scheduler_extra_filters: []

# This should be tuned depending on the number of compute hosts present in the
# deployment. Large clouds may wish to disable automatic discovery by setting
# this value to -1.
nova_discover_hosts_in_cells_interval: "{{ 300 if groups['nova_compute'] |
```

~~length > 10 else 60 }}~~

# Define nfs information to enable nfs shares as mounted directories for
# nova. The ``nova\_nfs\_client`` value is a list of dictionaries that must
# be filled out completely to enable the persistent NFS mounts.
#
# Example of the expected dict structure:
# **nova\_nfs\_client:**
# - server: "127.0.0.1" ## Hostname or IP address of NFS
~~server~~
# remote\_path: "/instances" ## Remote path from the NFS server
~~remote\_path~~
# export: ## Local path on machine
# type: "nfs" ## This can be nfs or nfs4
# options: "\_netdev,auto" ## Mount options
# config\_overrides: "{}" ## Override dictionary for unit
~~config\_overrides~~
~~file~~
**nova\_nfs\_client:** []

# Nova Ceph rbd
# Enable and define nova\_libvirt\_images\_rbd\_pool to use rbd as nova backend
**nova\_libvirt\_images\_rbd\_pool:** vms
**nova\_ceph\_client:** "{{ cinder\_ceph\_client }}"

# Enabled upstream if RBD is in use on cinder backends, which requires that
# ceph be deployed on the nova compute hosts to enable volume backed
~~instances~~
**nova\_cinder\_rbd\_inuse:** False

# Enable compute nodes to retrieve images from RBD directly rather than
~~through~~
# HTTP if images\_type is NOT set to RBD. Must be False if nova images stored
~~in RBD~~.
**nova\_glance\_rbd\_inuse:** False
**nova\_glance\_images\_rbd\_pool:** "{{ glance\_rbd\_store\_pool | default('images') }}"

(continues on next page)

(continued from previous page)

```

# Used to determine if we need a Ceph client
nova_rbd_inuse: "{{ (nova_libvirt_images_rbd_pool | length > 0) or (nova_
˓→cinder_rbd_inuse | bool) }}"

## General Nova configuration
# If ``nova_conductor_workers`` is unset the system will use half the number of_
˓→available VCPUS to
# compute the number of api workers to use.
# nova_conductor_workers: 16

# If ``nova_scheduler_workers`` is unset the system will use half the number of_
˓→available VCPUS to
# compute the number of api workers to use.
# nova_scheduler_workers: 16

## Cap the maximum number of threads / workers when a user value is_
˓→unspecified.
nova_api_threads_max: 16
nova_api_threads: "{{ [(ansible_facts['processor_vcpus'])//ansible_facts[_
˓→'processor_threads_per_core'])|default(1), 1] | max * 2, nova_api_threads_
˓→max] | min }}"

## Policy vars
# Provide a list of access controls to update the default policy.json with.__
˓→These changes will be merged
# with the access controls in the default policy.json. E.g.
#nova_policy_overrides:
#   "compute:create": ""
#   "compute:create:attach_network": ""

nova_service_in_ldap: "{{ service_ldap_backend_enabled | default(False) }}"

## libvirtd config options
nova_libvirtd_listen_tls: 1
nova_libvirtd_listen_tcp: 0
nova_libvirtd_auth_tcp: sasl
nova_libvirtd_debug_log_filters: "3:remote 4:event 3:json 3:rpc"

nova_api_metadata_init_overrides: {}
nova_api_os_compute_init_overrides: {}
nova_compute_init_overrides: {}
nova_conductor_init_overrides: {}
nova_novncproxy_init_overrides: {}
nova_scheduler_init_overrides: {}
nova_spicehtml5proxy_init_overrides: {}
nova_serialproxy_init_overrides: {}

## Service Name-Group Mapping

```

(continues on next page)

(continued from previous page)

```

nova_services:
  nova-api-metadata:
    group: nova_api_metadata
    service_name: nova-api-metadata
    init_config_overrides: "{{ nova_api_metadata_init_overrides }}"
    start_order: 5
    wsgi_app: True
    uwsgi_overrides: "{{ nova_api_metadata_uwsgi_ini_overrides }}"
    uwsgi_bind_address: "{{ nova_metadata_bind_address }}"
    uwsgi_port: "{{ nova_metadata_port }}"
    wsgi_name: nova-metadata-wsgi
  nova-api-os-compute:
    group: nova_api_os_compute
    service_name: nova-api-os-compute
    init_config_overrides: "{{ {'Install': {'Alias': 'nova-api.service'}} | _"
    →combine(nova_api_os_compute_init_overrides, recursive=True) }}"
    start_order: 4
    wsgi_app: True
    uwsgi_overrides: "{{ nova_api_os_compute_uwsgi_ini_overrides }}"
    uwsgi_bind_address: "{{ nova_service_bind_address }}"
    uwsgi_port: "{{ nova_service_port }}"
    wsgi_name: nova-api-wsgi
  nova-compute:
    group: nova_compute
    service_name: nova-compute
    init_config_overrides: "{{ nova_compute_init_overrides }}"
    start_order: 6
    execstarts: "{{ nova_bin }}/nova-compute"
    execreloads: "/bin/kill -HUP $MAINPID"
    after_targets:
      - libvirtd.service
      - syslog.target
      - network.target
  nova-conductor:
    group: nova_conductor
    service_name: nova-conductor
    init_config_overrides: "{{ nova_conductor_init_overrides }}"
    start_order: 2
    execstarts: "{{ nova_bin }}/nova-conductor"
    execreloads: "/bin/kill -HUP $MAINPID"
  nova-novncproxy:
    group: nova_console
    service_name: nova-novncproxy
    init_config_overrides: "{{ nova_novncproxy_init_overrides }}"
    condition: "{{ nova_console_type == 'novnc' }}"
    start_order: 5
    execstarts: "{{ nova_bin }}/nova-novncproxy"
  nova-scheduler:
    group: nova_scheduler

```

(continues on next page)

(continued from previous page)

```

service_name: nova-scheduler
init_config_overrides: "{{ nova_scheduler_init_overrides }}"
start_order: 3
execstarts: "{{ nova_bin }}/nova-scheduler"
execreloads: "/bin/kill -HUP $MAINPID"

nova-spicehtml5proxy:
  group: nova_console
  service_name: nova-spicehtml5proxy
  init_config_overrides: "{{ {'Install': {'Alias': 'nova-spiceproxy.service'}} | combine(nova_spicehtml5proxy_init_overrides, recursive=True) }}"
  condition: "{{ nova_console_type == 'spice' }}"
  start_order: 5
  execstarts: "{{ nova_bin }}/nova-spicehtml5proxy"

nova-serialconsole-proxy:
  group: nova_console
  service_name: nova-serialproxy
  init_config_overrides: "{{ nova_serialproxy_init_overrides }}"
  condition: "{{ nova_console_type == 'serialconsole' }}"
  start_order: 5
  execstarts: "{{ nova_bin }}/nova-serialproxy"

nova_novnc_pip_packages:
  - websockify

nova_compute_ironic_pip_packages:
  - python-ironicclient

# Common pip packages
nova_pip_packages:
  - "git+{{ nova_git_repo }}@{{ nova_git_install_branch }}#egg=nova"
  - oslo.profiler
  - PyMySQL
  - pymemcache
  - python-memcached
  - systemd-python

# Specific pip packages provided by the user
nova_user_pip_packages: []

nova_optional_oslomsg_amqp1_pip_packages:
  - oslo.messaging[amqp1]

nova_qemu_user: libvirt-qemu
nova_qemu_group: kvm

# Define the following variable to drop a replacement
# file for /etc/libvirt/qemu.conf
qemu_conf_dict: {}

```

(continues on next page)

(continued from previous page)

```

## Tunable overrides
nova_nova_conf_overrides: {}
nova_rootwrap_conf_overrides: {}
nova_api_paste_ini_overrides: {}
nova_policy_overrides: {}
nova_vendor_data_overrides: {}
nova_api_metadata_uwsgi_ini_overrides: {}
nova_api_os_compute_uwsgi_ini_overrides: {}

# Enabled vGPU Types - dict defining 'type' and 'address' (optional) of vGPU
# an address is only required when supporting more than one physical GPU on
# the host
# Example 1:
# nova_enabled_mdev_types:
#   - type: nvidia-35
#
# Example 2:
# nova_enabled_mdev_types:
#   - type: nvidia-35
#     address: "<device address.0>,<device address.1>"
#   - type: nvidia-36
#     address:
#       - "<another device address.0>"
#       - "<another device address.1>"
nova_enabled_mdev_types: "{{ nova_enabled_vgpu_types | default({}) }}"

# PCI devices passthrough to nova
# For SR-IOV please use:
#   nova_pci_passthrough_whitelist: '{ "physical_network": "<ml2 network name>",
#                                         "devname": "<physical nic>" }'
# Example:
#   nova_pci_passthrough_whitelist: '{ "physical_network": "physnet1",
#                                         "devname": "p1p1" }'
nova_pci_passthrough_whitelist: {}

# PCI alias,
# Example:
# nova_pci_alias:
#   - '{ "name": "card-alias1", "product_id": "XXXX", "vendor_id": "XXXX" }'
#   - '{ "name": "card-alias2", "product_id": "XXYY", "vendor_id": "XXYY" }'
nova_pci_alias: []

# Storage location for SSL certificate authority
nova_pki_dir: "{{ openstack_pki_dir }}"

# Delegated host for operating the certificate authority
nova_pki_setup_host: "{{ openstack_pki_setup_host | default('localhost') }}"

# Nova server certificate
nova_pki_keys_path: "{{ nova_pki_dir ~ '/certs/private/' }}"

```

(continues on next page)

(continued from previous page)

```

nova_pki_certs_path: "{{ nova_pki_dir ~ '/certs/certs/' }}"
nova_pki_intermediate_cert_name: "{{ openstack_pki_service_intermediate_cert_
    ~name }}"
nova_pki_intermediate_chain_path: "{{ nova_pki_dir ~ '/roots/' ~ nova_pki_
    ~intermediate_cert_name ~ '/certs/' ~ nova_pki_intermediate_cert_name ~ '-_
    ~chain.crt' }}"
nova_pki_regen_cert: ''
# Create client and server cert for compute hosts
# This certificate is used to secure TLS live migrations and VNC sessions
nova_pki_compute_certificates:
  - name: "nova_{{ ansible_facts['hostname'] }}"
    provider: ownca
    cn: "{{ ansible_facts['nodename'] }}"
    san: "{{ 'DNS:' ~ ansible_facts['hostname'] ~ ',DNS:' ~ ansible_facts[_
        'nodename'] ~ ',IP:' ~ (nova_management_address == 'localhost') | ternary(_
        '127.0.0.1', nova_management_address) }}"
    signed_by: "{{ nova_pki_intermediate_cert_name }}"
    key_usage:
      - digitalSignature
      - keyAgreement
      - keyEncipherment
    extended_key_usage:
      - clientAuth
      - serverAuth

# libvirt default destination files for SSL certificates
nova_libvirt_ssl_dir: /etc/pki/libvirt
# QEMU default destination files for SSL certificates
nova_qemu_ssl_dir: /etc/pki/qemu

# Installation details for SSL certificates for compute hosts TLS live_
    ~migration
nova_pki_compute_install_certificates:
  - src: "{{ nova_user_ssl_cert | default(nova_pki_certs_path ~ 'nova_' ~_
    ansible_facts['hostname'] ~ '-chain.crt') }}"
    dest: "{{ nova_libvirt_ssl_dir }}/servercert.pem"
    owner: "root"
    group: "root"
    mode: "0640"
  # Server certificate key used by libvirt for live migrations
  - src: "{{ nova_user_ssl_key | default(nova_pki_keys_path ~ 'nova_' ~_
    ansible_facts['hostname'] ~ '.key.pem') }}"
    dest: "{{ nova_libvirt_ssl_dir }}/private/serverkey.pem"
    owner: "root"
    group: "root"
    mode: "0640"
  # Client certificate used by libvirt for live migrations
  # Defaults to using the server certificate which is signed for both_
    ~clientAuth and serverAuth

```

(continues on next page)

(continued from previous page)

```

- src: "{{ nova_user_ssl_cert | default(nova_pki_certs_path ~ 'nova_'
  ~ ansible_facts['hostname'] ~ '-chain.crt') }}"
  dest: "{{ nova_libvirt_ssl_dir }}/clientcert.pem"
  owner: "root"
  group: "root"
  mode: "0640"
# Client certificate key used by libvirt for live migrations
- src: "{{ nova_user_ssl_key | default(nova_pki_keys_path ~ 'nova_'
  ~ ansible_facts['hostname'] ~ '.key.pem') }}"
  dest: "{{ nova_libvirt_ssl_dir }}/private/clientkey.pem"
  owner: "root"
  group: "root"
  mode: "0640"
# Server certificate used by QEMU for live migrations
- src: "{{ nova_user_ssl_cert | default(nova_pki_certs_path ~ 'nova_'
  ~ ansible_facts['hostname'] ~ '-chain.crt') }}"
  dest: "{{ nova_qemu_ssl_dir }}/server-cert.pem"
  owner: "root"
  group: "{{ nova_qemu_group }}"
  mode: "0640"
# Server certificate key used by QEMU for live migrations
- src: "{{ nova_user_ssl_key | default(nova_pki_keys_path ~ 'nova_'
  ~ ansible_facts['hostname'] ~ '.key.pem') }}"
  dest: "{{ nova_qemu_ssl_dir }}/server-key.pem"
  owner: "root"
  group: "{{ nova_qemu_group }}"
  mode: "0640"
# Client certificate used by QEMU for live migrations
# Defaults to using the server certificate which is signed for both
# clientAuth and serverAuth
- src: "{{ nova_user_ssl_cert | default(nova_pki_certs_path ~ 'nova_'
  ~ ansible_facts['hostname'] ~ '-chain.crt') }}"
  dest: "{{ nova_qemu_ssl_dir }}/client-cert.pem"
  owner: "root"
  group: "{{ nova_qemu_group }}"
  mode: "0640"
# Client certificate key used by QEMU for live migrations
- src: "{{ nova_user_ssl_key | default(nova_pki_keys_path ~ 'nova_'
  ~ ansible_facts['hostname'] ~ '.key.pem') }}"
  dest: "{{ nova_qemu_ssl_dir }}/client-key.pem"
  owner: "root"
  group: "{{ nova_qemu_group }}"
  mode: "0640"
# Root CA for libvirt
# libvirt requires that the CA cert file has any intermediate certificates
# for the server cert,
# so defaults to using the intermediate chain, which contains the
# intermediate and Root CA
- src: "{{ nova_user_ssl_ca_cert | default(nova_pki_intermediate_chain_
  ~ path) }}"

```

(continues on next page)

(continued from previous page)

```

dest: "/etc/pki/CA/cacert.pem"
owner: "root"
group: "root"
mode: "0644"
# Root CA for qemu
- src: "{{ nova_user_ssl_ca_cert | default(nova_pki_intermediate_chain_
→path) }}"
  dest: "{{ nova_qemu_ssl_dir }}/ca-cert.pem"
  owner: "root"
  group: "root"
  mode: "0644"

# Define user-provided SSL certificates in:
# /etc/openstack_deploy/user_variables.yml
#nova_user_ssl_cert: <path to cert on ansible deployment host>
#nova_user_ssl_key: <path to cert on ansible deployment host>
#nova_user_ssl_ca_cert: <path to cert on ansible deployment host>

# TLS certificates for console hosts
nova_pki_console_certificates:
  # Client certificate used by novnv proxy to authenticate with compute hosts,
→using vncrypt
  - name: "nova_{{ ansible_facts['hostname'] }}-client"
    provider: ownca
    cn: "{{ ansible_facts['nodename'] }}"
    san: "{{ 'DNS:' ~ ansible_facts['hostname'] ~ ',DNS:' ~ ansible_facts[
→'nodename'] ~ ',IP:' ~ (nova_management_address == 'localhost') | ternary(
→'127.0.0.1', nova_management_address) }}"
    signed_by: "{{ nova_pki_intermediate_cert_name }}"
    key_usage:
      - digitalSignature
      - keyAgreement
      - keyEncipherment
    extended_key_usage:
      - clientAuth

# Installation details for SSL certificates for console hosts
nova_pki_console_install_certificates:
  - src: "{{ nova_user_ssl_cert | default(nova_pki_certs_path ~ 'nova_' ~
→ansible_facts['hostname'] ~ '-client-chain.crt') }}"
    dest: "{{ nova_vncrypt_client_cert }}"
    owner: "root"
    group: "{{ nova_system_group_name }}"
    mode: "0640"
  - src: "{{ nova_user_ssl_key | default(nova_pki_keys_path ~ 'nova_' ~
→ansible_facts['hostname'] ~ '-client.key.pem') }}"
    dest: "{{ nova_vncrypt_client_key }}"
    owner: "root"
    group: "{{ nova_system_group_name }}"

```

(continues on next page)

(continued from previous page)

```

mode: "0640"
- src: "{{ nova_user_ssl_ca_cert | default(nova_pki_intermediate_chain_
→path) }}"
  dest: "{{ nova_vencrypt_ca_certs }}"
  owner: "root"
  group: "{{ nova_system_group_name }}"
  mode: "0640"

# host which holds the ssh certificate authority
nova_ssh_keypairs_setup_host: "{{ openstack_ssh_keypairs_setup_host |_
→default('localhost') }}"

# directory on the deploy host to create and store SSH keypairs
nova_ssh_keypairs_dir: "{{ openstack_ssh_keypairs_dir | default('/etc/
→openstack_deploy/ssh_keypairs') }}"

#Each compute host needs a signed ssh certificate to log into the others
nova_ssh_keypairs:
- name: "nova-{{ inventory_hostname }}"
  cert:
    signed_by: "{{ openstack_ssh_signing_key }}"
    principals: "{{ nova_ssh_key_principals | default('nova') }}"
    valid_from: "{{ nova_ssh_key_valid_from | default('always') }}"
    valid_to: "{{ nova_ssh_key_valid_to | default('forever') }}"

#Each compute host needs the signed ssh certificate installing to the nova_
→user
nova_ssh_keypairs_install_keys:
  owner: "{{ nova_system_user_name }}"
  group: "{{ nova_system_group_name }}"
  keys:
    - cert: "nova-{{ inventory_hostname }}"
      dest: "{{ nova_system_home_folder }}/.ssh/id_rsa"

#Each compute host must trust the SSHD certificate authoritiy in the sshd_
→configuration
nova_ssh_keypairs_install_ca: "{{ openstack_ssh_keypairsAuthorities }}"

#Each compute host must allow SSH certificates with the appropriate principal_
→to log into the nova user
nova_ssh_keypairs_principals:
- user: "{{ nova_system_user_name }}"
  principals: "{{ nova_ssh_key_principals | default(['nova']) }}"

```



---

**CHAPTER  
THREE**

---

**DEPENDENCIES**

This role needs pip >= 7.1 installed on the target host.



---

CHAPTER  
FOUR

---

## EXAMPLE PLAYBOOK

```
---
```

```
- name: Installation and setup of Nova
  hosts: nova_all
  user: root
  roles:
    - { role: "os_nova", tags: [ "os-nova" ] }
  vars:
    nova_galera_address: "{{ internal_lb_vip_address }}"
    galera_root_user: root
  vars_prompt:
    - name: "galera_root_password"
      prompt: "What is galera_root_password?"
```



---

**CHAPTER  
FIVE**

---

**TAGS**

This role supports two tags: **nova-install** and **nova-config**

The **nova-install** tag can be used to install and upgrade.

The **nova-config** tag can be used to manage configuration.



---

**CHAPTER  
SIX**

---

## **CPU PLATFORM COMPATIBILITY**

This role supports multiple CPU architecture types. At least one repo\_build node must exist for each CPU type that is in use in the deployment.

**Currently supported CPU architectures:**

- x86\_64 / amd64
- ppc64le

At this time, ppc64le is only supported for the Compute node type. It can not be used to manage the OpenStack-Ansible management nodes.



## COMPUTE DRIVER COMPATIBILITY

This role supports multiple nova compute driver types. The following compute drivers are supported:

- libvirt (default)
- ironic

The driver type is automatically detected by the OpenStack Ansible Nova role for the following compute driver types:

- libvirt (kvm / qemu)

Any mix and match of compute node types can be used for those platforms, except for ironic.

The `nova_virt_type` may be set in `/etc/openstack_deploy/user_variables.yml`, for example:

```
nova_virt_type: ironic
```

You can set `nova_virt_type` per host by using `host_vars` in `/etc/openstack_deploy/openstack_user_config.yml`. For example:

```
compute_hosts:  
  aio1:  
    ip: 172.29.236.100  
    host_vars:  
      nova_virt_type: ironic
```

If `nova_virt_type` is set in `/etc/openstack_deploy/user_variables.yml`, all nodes in the deployment are set to that hypervisor type. Setting `nova_virt_type` in both `/etc/openstack_deploy/user_variables.yml` and `/etc/openstack_deploy/openstack_user_config.yml` will always result in the value specified in `/etc/openstack_deploy/user_variables.yml` being set on all hosts.